



# FioranoMQ

**Fiorano**  
Enabling change at the speed of thought

[www.fiorano.com](http://www.fiorano.com)

## Reference Guide

### AMERICA'S

Fiorano Software, Inc.  
230 S. California Avenue,  
Suite 103, Palo Alto,  
CA 94306 USA  
Tel: +1 650 326 1136  
Fax: +1 646 607 5875  
Toll-Free: +1 800 663 3621  
Email: [info@fiorano.com](mailto:info@fiorano.com)

### EMEA

Fiorano Software Ltd.  
3000 Hillswood Drive Hillswood  
Business Park Chertsey Surrey  
KT16 0RS UK  
Tel: +44 (0) 1932 895005  
Fax: +44 (0) 1932 325413  
Email: [info\\_uk@fiorano.com](mailto:info_uk@fiorano.com)

### APAC

Fiorano Software Pte. Ltd.  
Level 42, Suntec Tower Three 8  
Temasek Boulevard 038988  
Singapore  
Tel: +65 68292234  
Fax: +65 68292235  
Email: [info\\_asiapac@fiorano.com](mailto:info_asiapac@fiorano.com)

Entire contents © Fiorano Software and Affiliates. All rights reserved. Reproduction of this document in any form without prior written permission is forbidden. The information contained herein has been obtained from sources believed to be reliable. Fiorano disclaims all warranties as to the accuracy, completeness or adequacy of such information. Fiorano shall have no liability for errors, omissions or inadequacies in the information contained herein or for interpretations thereof. The opinions expressed herein are subject to change without prior notice.

Copyright (c) 1999-2007, Fiorano Software Private Limited. and Affiliates

Copyright (c) 2008-2012, Fiorano Software Pte Ltd. and Affiliates

All rights reserved.

This software is the confidential and proprietary information of Fiorano Software ("Confidential Information"). You shall not disclose such Confidential Information and shall use it only in accordance with the terms of the license agreement enclosed with this product or entered into with Fiorano.



# Contents

---

## Chapter 1: Connection Factory Configuration..... 19

AddShutdownHook .....	19
AllowDurableConnections .....	19
AutoDispatchConnections .....	20
Backup ConnectURLs .....	20
BatchTimeoutInterval.....	21
BatchingEnabled.....	21
BlockPublisherRetryInterval .....	21
ClientProxyURL .....	21
CompressionManager.....	22
Connection ClientID .....	22
CreateLocalSocket .....	22
Disable Ping.....	22
DisableSendingCSPStoredMessages .....	23
DurableConnectionReconnectInterval .....	24
DurableConnectionsBaseDir .....	24
EnableAutoRevalidation .....	24
EnableLMS.....	25
HTTPProxyURL .....	25
isThreadContextClassLoaderUsed .....	25
java.naming.security.protocol .....	25
LookupPreferredServer.....	25
MaxAdminConnectionReconnectAttempts.....	26
MaxBlockPublisherRetryAttempts.....	26
MaxDurableConnectionReconnectAttempts .....	26
MaxSocketCreationTries .....	27
ProxyAuthenticationRealm .....	27
ProxyCredentials .....	27
ProxyPrincipal .....	27
ProxyType .....	27
PublishBehaviourInAutoRevalidation .....	28
PublishWaitDuringCSPSyncup .....	28
SecurityManager .....	29
ServerProxyURL .....	29
SleepBetweenSocketCreationTries .....	29
SocketKeepAliveEnabled.....	29
SocketTimeout .....	30
SocksProxyURL .....	30
TCPBatchSize.....	30
TransportProtocol .....	30

---

UseFioranoCbr .....	30
UpdateConnectURL .....	31
UseLocalProcedureCalls .....	31
UseSingleSocketForSendReceive .....	31
XASocketTimeout .....	31

## Chapter 2: Common FioranoMQ Configuration..... 33

FMQConfigLoader .....	33
AclBasedDestinationSecurity .....	33
AllowDurableConnections .....	33
AllPermissions .....	34
AllowOnTheFlyAclCheck .....	34
AllowOnTheFlyCreationOfDestinations.....	35
CreateDefaultACL.....	36
EnableAutoRevalidation .....	36
EnsureUniquenessOfClientId.....	36
HttpPollingInterval .....	37
IncludeMessageID .....	37
LazyRSCreation .....	37
MaxTransactionBufferSize .....	37
MessageSelectorFactoryClassName .....	38
PingEnabled .....	38
ResumeTimeoutInterval.....	38
SSEnabled .....	38
SystemEncodingFormat .....	39
UseFioranoCbr .....	39
UseSingleSocket .....	40
UseSingleSocketForAdmin.....	40

## Chapter 3: Queue Subsystem Level Configurations .... 41

UnAckedQueueBufferSize .....	41
MaxNumberOfQueues .....	41
RedeliveryTriesOnListenerException.....	41
DelayInMsgDeliveryOnListenerException .....	42
Dependencies occur only in when the client session is either in AUTO_ACK or DUPS_OK_ACKNOWLEDGE modes.CleanupDmqAtStartup.....	42
EnableSnooperOnAllQueues .....	43
EnableDMQOnAllQueues .....	43
PrefetchCount .....	44
PrefetchThreshold.....	44
DefaultStorageTypeForQueues .....	44
MaxPrefetchSize .....	45
OverflowFromBottomEnabled .....	45

---

DMQExpiryTime.....	45
Restart of server required: TRUEEnableNotificationOnDeadMessage.....	46
Restart of server required: FALSEEnableMessageMonitoring.....	46
FilePath.....	46
TimeDuration.....	46
CleanupInterval.....	47
InMemoryBlockingInterval.....	47
InMemoryBufferSize.....	47
PersistentInMemoryBufferSize.....	48
MaxPushAttempts.....	48
WaitBetweenAttempts.....	48
IsDbCleanupEnabled.....	48
UseInMemStatusCache.....	49
LoadBitSetOnStartup.....	49
EnableGMSQueueExpose.....	49
Exclusive.....	49
JumpDeletedFiles.....	50
DepthMonitoringEnabled.....	50
DepthMonitoringLevels.....	50

## Chapter 4: Queue Level Configurations..... 52

EnableJournaling.....	52
StoreNPMessagesInDb.....	52
QueueLimitReachedNotificationThreshold.....	52
QueueBehaviorOnBufferOverflow.....	53
ForcePushWait.....	53
QueueIdleStateNotifierThresholdTime.....	53
DupsOkBatchSize.....	54
RedeliveryTriesOnListenerException.....	54
DelayInMsgDeliveryOnListenerException.....	55
PublishWait.....	55
PublishWaitTimeRecheckUnits.....	56
MaxNumberOfTopics.....	56
EnablePublisherSlowdown.....	57
DropOldestMessage.....	57
DefaultStorageTypeForTopics.....	57
StoreMessageToDisk.....	58
EnableSnooperOnAllTopics.....	58
EventTopicName.....	58
IsForceFullyKillIDSubscriber.....	59
MaxPersistentStoreSize.....	59
UseMessagePersisterForDurableSubscriber.....	59
MaxMsgInOneRecv.....	60
BasicAllowedSize.....	60
UseOptimizedTCPReceive.....	60

---

EnableMessageMonitoring.....	60
FilePath.....	61
TimeDuration.....	61
PurgeLevelIndex.....	61
MinPurgeDifference.....	61
AllowDeletionOfSubtopics.....	62
MessagePublishTimeout.....	62
PublishBackoffThreshold.....	62
IgnorePSQSizeForPersistentMessages.....	63
EnableSessionStateChangeNotification.....	63
LoadLVCIndicesAtLookup.....	63
IgnoreNullLVCKey.....	64
FlushLVCDDataAtStartup.....	64

## Chapter 6: Topic Level Configurations ..... 66

CacheKeyPropertyName.....	66
CachePropertyName.....	66
EnableLastValueCache.....	66
EnableJournaling.....	67
MaxPublisherBlockTime.....	67
ParConsumptionLVCache.....	67

## Chapter 7: Connection Manager Configurations ..... 68

Default.....	68
CFNameAppender (Not being used in FioranoMQ).....	68
ReaderCacheDisabled.....	68
TCPWindowSize (Not being Used in FioranoMQ).....	69
HandshakeInWorkerThread.....	69
MagicTimeout.....	69
Port.....	69
Protocol.....	70
UseNagle.....	70
MonitoringRequest.....	70
MonitoringResponse.....	71
EnforceJsseAuthentication.....	71
MaxClientConnectionsCount.....	71
AdminConnection (Not being used).....	72
Path.....	72
ServerAddress.....	72
HandShakingDisabled.....	72
ManagerClassName.....	73
FioranoMQServer.....	73
UseForPeerToPeerCommunication (Not being used in FioranoMQ).....	74

---

UseSystemPropsForSSL.....	74
CipherSuiteList.....	74

## Chapter 8: Dash Board Configurations..... 75

JettyServer.....	75
MaxThreads.....	75
EnableStart.....	75
MinThreads.....	76
LowThreads.....	76
MaxIdleTime.....	76
LowResourceMaxIdleTime.....	76
PortNumber.....	77

## Chapter 9: Security Configuration ..... 78

SecuritySubSystem.....	78
UseAuthenticationModules.....	78
ConfigurationName.....	78
ConfigurationFileName.....	78
NativeFileBasedAclManager.....	79
MaxAcePerAcl.....	79
LdapBasedAclManager.....	79
LdapProviderUrl.....	79
LdapProviderDn.....	79
Principal.....	80
Credentials.....	80
LdapInitialCtxFactory.....	80
LdapAclContextDn.....	80
LdapSecurityAuthentication.....	81
LdapPollInterval.....	81
LdapPrimaryServerReconnectAttempts.....	81
BackupLdapProviderUrl.....	81
BackupLdapProviderDn.....	81
BackupPrincipal.....	82
BackupCredentials.....	82
BackupLdapInitialCtxFactory.....	82
BackupLdapSecurityAuthentication.....	82
AclEntryObjectClasses.....	82
XMLFileBasedAclManager.....	83
Path.....	83
Filename.....	83
MaxAcePerAcl.....	83
RdbmsBasedAclManager.....	83
MaxAcePerAcl.....	83

---

Url .....	83
Password .....	84
Username .....	84
DBDriver.....	84
ConnectionTimeoutInterval .....	84
ReconnectTimeInterval .....	84
EnableReconnect .....	84
StatementFile.....	85
ConnectionLostErrorMessage .....	85
InitializeDB .....	85
FileDBManager3 .....	85
Path .....	85
DeletedThresholdPercent .....	86
DeletedThresholdCount.....	86
DbTableNamePrefix .....	87
NativeFilePrincipalManager .....	87
MaxPasswordLength .....	87
MaxMemberCount .....	87
LdapPrincipalManager .....	88
LdapProviderUrl .....	88
LdapProviderDn.....	88
Principal .....	88
Credentials .....	88
LdapInitialCtxFactory .....	89
LdapSecurityAuthentication .....	89
LdapPollInterval .....	89
LdapPrimaryServerReconnectAttempts.....	89
BackupLdapProviderUrl .....	89
BackupLdapProviderDn .....	90
BackupPrincipal .....	90
BackupCredentials.....	90
BackupLdapInitialCtxFactory .....	90
BackupLdapSecurityAuthentication .....	90
LdapUserClassTop .....	91
LdapUserClassPerson .....	91
LdapUserClassOrganizationalPerson .....	91
LdapUserClassInetorgPerson.....	91
LdapGroupClassTop .....	91
LdapGroupClassUniqueNames .....	92
LdapGroupClassUniqueMember .....	92
LdapUserNameAttribute .....	92
LdapUserPasswordAttribute .....	92
LdapGroupNameAttribute .....	92
LdapGroupUserNameAttribute .....	93
LdapUserDn.....	93
LdapGroupDn.....	93

---



XMLFilePrincipalManager .....	93
Path .....	93
Username .....	93
GroupFilename .....	94
PrincipalManagerRDBMS .....	94
Url .....	94
Password .....	94
Username .....	94
DBDriver .....	94
ConnectionTimeoutInterval .....	94
ReconnectTimeInterval .....	94
EnableReconnect .....	95
StatementFile .....	95
ConnectionLostErrorMessage .....	95
InitializeDB .....	95
FileDBManager2 .....	96
Path .....	96
DeletedThresholdPercent .....	96
DeletedThresholdCount .....	97
DbTableNamePrefix .....	97

## Chapter 10: Logger Configuration ..... 98

Introduction .....	98
AppenderAdditive .....	101
LogLevel .....	101
LogAppender .....	102
AppenderName .....	102
AppenderType .....	102
LogPattern .....	102
ThresholdLevel .....	103
FilterPattern .....	103
PrintTarget .....	103
FileName .....	104
IsAppend .....	104
MaxBackupIndex .....	104
MaxFileSize .....	105
MaxFilterLevel .....	105
MinFilterLevel .....	105
LogAppender .....	106
AppenderName .....	106
AppenderType .....	106
LogPattern .....	106
ThresholdLevel .....	106
FilterPattern .....	107
PrintTarget .....	107

---

FileName .....	107
IsAppend .....	108
MaxBackupIndex .....	108
MaxFileSize .....	109
MaxFilterLevel .....	109
MinFilterLevel .....	109

## Chapter 11: HA Replicated Configuration ..... 110

Primary Server Configuration .....	110
FioranoHAConnectionManager .....	110
Port .....	110
NagleAlgo.....	110
SocketInitializationTimeout.....	111
QGMSSubManager .....	111
MinServiceID .....	111
MaxServiceID .....	112
TGMSSubManager.....	112
MinServiceID .....	112
MaxServiceID .....	112
SyncRealmStubManager .....	113
MinServiceID .....	113
MaxServiceID .....	113
SyncNamingStubManager .....	113
MinServiceID .....	113
MaxServiceID .....	114
MinServiceID .....	114
MaxServiceID .....	114
SyncQueueStubManager .....	115
MinServiceID .....	115
MaxServiceID .....	115
RpStateStubManager.....	115
MinServiceID .....	116
MaxServiceID .....	116
FioranoRpRealmManager .....	116
AclZipPath .....	116
AclUnzipDir.....	117
PrincipalZipPath .....	117
PrincipalUnzipDir .....	117
SocketTimeout.....	118
FioranoRpNamingManager .....	118
ZipPath .....	118
UnzipDir.....	118
SocketTimeout.....	119
FioranoHAKRPCProvider .....	119
BackupHAPort .....	119

---

BackupHAIPAddress.....	119
SocketTimeout.....	119
SocketCreationTimeout.....	120
HaStateNotifBroadcaster.....	120
LoggerName.....	120
FioranoStatusPersister.....	120
Path.....	120
FioranoHAManager.....	121
Primary.....	121
GatewayListenerNotUpMesg.....	121
PingInterval.....	122
GatewayServerPort.....	122
SocketCreationTimeout.....	122
ServerName.....	122
GatewayServerIPAddress.....	123
MaxWaitTimeout.....	123
WaitTimeForBackupServer.....	123
MaxPingCount.....	124
FioranoFMQKernel.....	124
MQUnDeploymentLists.....	124
ExternalUnDeploymentLists.....	125
MQDeploymentLists.....	125
ExternalDeploymentLists.....	126
FioranoRpTopicManager.....	126
ZipPath.....	126
UnzipDir.....	126
SocketTimeout.....	127
FioranoRpQueueManager.....	127
ZipPath.....	127
UnzipDir.....	128
SocketTimeout.....	128
Secondary Server Configuration.....	128
FioranoHAConnectionManager.....	128
Port.....	128
NagleAlgo.....	129
SocketInitializationTimeout.....	129
SyncTopicStubManager.....	129
MinServiceID.....	130
MaxServiceID.....	130
RealmStubManager.....	130
MaxServiceID.....	130
QGMSStubManager.....	131
MinServiceID.....	131
MaxServiceID.....	131
TGMSSStubManager.....	131
MinServiceID.....	131

---

MaxServiceID .....	132
MinServiceID .....	132
MaxServiceID .....	132
SyncNamingStubManager .....	133
MinServiceID .....	133
MaxServiceID .....	133
NamingStubManager .....	133
MinServiceID .....	133
MaxServiceID .....	134
SyncQueueStubManager .....	134
MinServiceID .....	134
MaxServiceID .....	134
RpStateStubManager .....	134
MinServiceID .....	135
MaxServiceID .....	135
FioranoRpRealmManager .....	135
AclZipPath .....	135
AclUnzipDir .....	136
PrincipalZipPath .....	136
PrincipalUnzipDir .....	136
SocketTimeout .....	137
FioranoRpNamingManager .....	137
ZipPath .....	137
UnzipDir .....	137
SocketTimeout .....	138
FioranoHAKRPCProvider .....	138
BackupHAPort .....	138
BackupHAIPAddress .....	138
SocketTimeout .....	139
SocketCreationTimeout .....	139
HaStateNotifBroadcaster .....	139
LoggerName .....	139
FioranoStatusPersister .....	139
Path .....	140
FioranoHAManager .....	140
Primary .....	140
GatewayListenerNotUpMesg .....	140
PingInterval .....	141
GatewayServerPort .....	141
SocketCreationTimeout .....	141
ServerName .....	142
GatewayServerIPAddress .....	142
MaxWaitTimeout .....	143
FioranoFMQKernel .....	143
MQUnDeploymentLists .....	143
ExternalUnDeploymentLists .....	144

---

MQDeploymentLists .....	144
ExternalDeploymentLists .....	145
FioranoRpTopicManager .....	145
ZipPath .....	145
UnzipDir .....	145
SocketTimeout .....	146
FioranoRpQueueManager .....	146
ZipPath .....	146
UnzipDir .....	147
SocketTimeout .....	147

## Chapter 12: HA Shared Configuration ..... 148

Primary Server Configuration .....	148
FioranoHAKRPCProvider .....	148
BackupHAPort .....	148
BackupHAIPAddress .....	148
SocketTimeout .....	148
SocketCreationTimeout .....	149
FioranoHAConnectionManager .....	149
Port .....	149
NagleAlgo .....	149
SocketInitializationTimeout .....	150
FioranoHASStateStubManager .....	150
MinServiceID .....	150
MaxServiceID .....	151
FioranoHAManager .....	151
Primary .....	151
GatewayListenerNotUpMesg .....	151
GatewayServerPort .....	152
PingInterval .....	152
SocketCreationTimeout .....	152
ServerName .....	153
GatewayServerIPAddress .....	153
FioranoFMQKernel .....	153
MQUnDeploymentLists .....	153
ExternalUnDeploymentLists .....	154
MQDeploymentLists .....	154
ExternalDeploymentLists .....	155
Secondary Server Configuration .....	155
FioranoHAKRPCProvider .....	155
BackupHAPort .....	155
BackupHAIPAddress .....	156
SocketTimeout .....	156
SocketCreationTimeout .....	156
FioranoHAConnectionManager .....	156

---

Port .....	156
NagleAlgo.....	157
SocketInitializationTimeout.....	157
FioranoHAManager .....	157
Primary .....	158
GatewayListenerNotUpMesg.....	158
GatewayServerPort.....	158
PingInterval .....	159
SocketCreationTimeout .....	159
ServerName .....	159
GatewayServerIPAddress .....	159
FioranoFMQKernel .....	160
MQUnDeploymentLists .....	160
ExternalUnDeploymentLists .....	161
MQDeploymentLists .....	161
ExternalDeploymentLists .....	162

## Chapter 13: Dispatcher Configuration..... 163

FioranoJobManager2 .....	163
MinimumJobWorkers .....	163
MaximumJobWorkers .....	163
Dispatcher.....	164
Name .....	164
PingTimeoutAttribute.....	164
InitialTimeoutAttribute.....	164

## Chapter 14: Repeater Configuration ..... 166

FioranoRepeaterManager .....	166
Name .....	166
DurableSubscriptionInfoFileName.....	166
PingInterval .....	166
AvoidLoopback .....	167
TransactionSize .....	167
TransactionTimeout.....	167
SourceServer .....	168
Name .....	168
ConnectionInfo.....	168
ProtocolType .....	168
JMXProtocol .....	168
JMXPort .....	168
ServerURL .....	169
UserName.....	169
Password .....	169

---

TopicConnectionFactory .....	169
ServerSecurityManager.....	170
ProxyURLAttribute.....	170
ServerSecurityManager parameter LinkTopicInfo .....	170
IsDurable.....	170
ConnectionMode .....	170
Type .....	171
ReplyOn.....	171
SourceTopicName .....	171
TargetTopicName.....	171
MessageSelector .....	172

## Chapter 15: Bridge Configurations..... 173

ConnectionInfo.....	173
ServerType .....	173
ProviderUrl.....	173
InitialContextFactory .....	173
BridgeUser .....	174
BridgePassword .....	174
QCF .....	174
Protocol .....	174
SecurityPrincipal .....	174
SecurityCredentials .....	174
ServerSecurityManager.....	175
QueueInfo .....	175
MsgSelector .....	175
QueueName .....	175

## Chapter 16: JMX Connector Configuration ..... 176

JMS Based Connector Configuration .....	176
InterceptorClassName .....	176
SecurityProtocol.....	176
Protocol .....	177
SecurityManagerClass .....	177
QueueConnectionFactory .....	177
ServerPort .....	178
ServerAddress .....	178
Username .....	178
Password .....	178
ConnectQueueName.....	178
RequestQueueName.....	178
NotifQueueName .....	179
RMI Based Connector Configuration .....	179

---

RMIServerPort .....	179
InterceptorClassName .....	179
RmiPortExportObjects.....	179
Hostname .....	179
RmiServerSocketFactoryClassName .....	180
RmiClientSocketFactoryClassName.....	180
JMX Engine Configuration .....	180
SecurityProtocol.....	180
Protocol .....	180
SecurityManagerClass .....	181
QueueConnectionFactory .....	181
ServerPort .....	181
ServerAddress .....	181
Username .....	182
Password .....	182
ConnectQueueName.....	182
RequestQueueName.....	182
NotifQueueName .....	182

## Chapter 17: Advanced Configuration..... 183

Route Manager Configuration .....	183
MaxTopicBuffer.....	183
RdbmsManager Configurations .....	183
URL.....	183
JdbcDriver .....	183
Password .....	184
Username .....	184
MaxConnections.....	184
DefaultConnections .....	184
MaxNoOfRowsFetch.....	184
EnableReconnect .....	185
ReconnectTimeInterval .....	185
WaitTime .....	185
ConnectionTimeoutInterval .....	186
PropertiesFilename.....	186
DbConnectivityQuery.....	186
EnableRdbms .....	186
Resource Manager Configurations.....	187
TimeInterval .....	187
EnableMonitoringThread .....	187
EnableVerboseLogging.....	188
EnableThreadDumpInfo .....	188
PingManager Configurations.....	188
PingTimeout.....	188
JobManager Configurations.....	189

---



MinimumJobWorkers .....	189
MaximumJobWorkers .....	189
JobsPerWorker .....	189
ObjectManager Configurations .....	190
HashCodeReuseAlgoUsed .....	190
ThreadManager Configurations.....	190
DelayBetweenAttempts.....	190
MaximumAttempts.....	191
MaxIdleThreads .....	191
DefaultLogManager Configurations.....	191
LogDir .....	191
Encoding.....	192
Level .....	192
FileSizeLimit.....	192
FileCount .....	193
AppendToFile.....	193
Formatter .....	193
MQ Default Object Creator Configurations.....	194
AutoUpdationAllowedForCFs .....	194
BackupServerIp .....	194
BackupServerPort .....	194
Timer Service Configurations .....	195
Name .....	195
ClockTick .....	195
JNDI Configurations .....	195
NativeFileNamingManager.....	195
DefragmentationLowerThreshold .....	195
DefragmentationUpperThreshold .....	196
DefragmentationPercentage.....	196
Path .....	196
CacheNamingManager .....	197
TTL.....	197
XMLFileNamingManager.....	197
Path .....	197
Filename .....	197
LDAPNamingManager .....	198
LdapProviderUrl .....	198
LdapBasedn.....	198
Principal.....	198
Credentials .....	198
LdapInitialCtxFactory .....	198
LdapPollInterval .....	199
LdapPrimaryServerReconnectAttempts.....	199
BackupLdapProviderUrl .....	199
BackupLdapBasedn.....	200
BackupPrincipal.....	200

---

BackupCredentials .....	200
BackupLdapInitialCtxFactory .....	200
TopicCFBaseDn .....	201
QueueCFBaseDn.....	201
AdminCFBaseDn.....	201
UnifiedCFBaseDn .....	201
TopicsBaseDn .....	202
QueueBaseDn .....	202
RDBMSNamingManager .....	202
URL .....	202
Password.....	203
Username.....	203
DatabaseDriver .....	203
SQLStatementFile.....	203
ConnectionLostErrorMessage .....	203
EnableReconnect .....	203
DatabaseConnectionTimeout.....	204
InitializeDB.....	204
Connection Consumer Configuration .....	204
FileDBManager5.....	204
Path .....	205
DeletedThresholdPercent .....	205
DeletedThresholdCount .....	206
DbTableNamePrefix .....	206
Directory Service.....	206
EnableCluster .....	206
EnableProfileMonitoring .....	207
DirectoryServiceAddress .....	207
DirectoryServicePort .....	207
SecurityPrincipal .....	207
SecurityCredentials .....	207
AuthenticationMode.....	207
InstancePath .....	208
SynchPeriodMillis .....	208
Monitoring Manager Configuration .....	208
ClockTickForMonitoring .....	208

---

# Chapter 1: Connection Factory Configuration

---

This chapter explains the parameters that can be configured at the Connection Factory level. Each connection that is created to the FioranoMQ Server using the connection factory inherits the parameters that are configured for the connection factory.

For information on how to create and configure Connection Factories in FioranoMQ using Studio, refer to section **23.2 Working with Connection Factories** of *FioranoMQ Handbook*.

## AddShutdownHook

Boolean used to enable/disable shut down hook in the client.

Enabling this parameter ensures that the program exits normally when the non-daemon thread exits or when the exit method is invoked. This also makes sure that connections and sockets are closed properly when the virtual machine is terminated in response User interruption such as typing ^C or a system-wide event such as User log off or system shutdown.

### Valid values:

- **yes** - enables shutdown hook.
- **no** - disables shutdown hook. This is the default value.
- **none** - uses the default value that is set in the Server.

### Default Value:

**No** - disables shutdown hook.

By default the shut down hook is disabled in client applications.

## AllowDurableConnections

AllowDurableConnections is the boolean value that is used to disable or enable durable connections for a particular client when the durable connections are enabled on the Server. When **AllowDurableConnections** is enabled, messages get stored into the Client Side Persistence (CSP) storage during the period that connection with the Server is down.

The parameter below is used to set the durable connections to true/false in a client.

The value set in the Connection Factory is overridden by the value set in the client application. The parameter below can also be set in the client application:

```
env.put(FioranoJNDIContext.ALLOW_DURABLE_CONNECTIONS, "true");
```

---

Here, **env** is a hashtable used to create the InitialContext which stores all the JNDI parameters.

**Valid values:**

- **yes** - enables durable connections in the client This is the default value.
- **no** - disables durable connections in the client.
- **none** - uses the default value that is set in the Server.

**Default Value:**

**yes** - enables durable connections in the client.

**Dependencies:**

This parameter is used for client side configuration.

If durable connections are disabled in the Server and enabled in client this disables all durable connections. If durable connections are enabled in the Server, their effect is dependent on the client configuration.

## AutoDispatchConnections

AutoDispatchConnections is the boolean value that is used to determine whether the dispatcher Server should be used for creating client connections. By default this flag is enabled. If set to true, the incoming client connections are automatically redirected to the least loaded Server that is registered to the dispatcher. If set to false, connections are created on the dispatcher without being redirected.

**Valid values:**

- **yes** - enables automatic dispatching of the connection.
- **no** - disables automatic dispatching of the connection.

**Dependencies:**

This parameter affects only the Dispatcher Server.

## Backup ConnectURLs

Backup ConnectURLs are URLs of the Backup Servers that are used in case the Primary Server is down. Multiple backup URLs may be used but need to be separated by the use of semicolons.

**Example:** Backup Connect URLs can be specified as:

http://backupServer1:1856;http://backupServer2:1856

---

## BatchTimeoutInterval

BatchTimeoutInterval is the time interval after which a batch of non-persistent messages will be sent irrespective of the size of the buffer.

Non-persistent messages are sent in batches to the Server. These batches are sent to the server when the batch size exceeds a particular size [default 32 bytes] or for the time specified by batchTimeoutInterval.

### Valid values:

Time is specified in milliseconds. The default time is 1000 milliseconds.

## BatchingEnabled

BatchingEnabled enables message batching algorithm in the client runtimes.

If batching is enabled, non-persistent messages are sent in groups to the server which results in higher message rates. Batching has no effect on persistent messages.

### Valid values:

- **true**: enables batching. This is the default value.
- **false**: disables batching.

**Default value:** true

## BlockPublisherRetryInterval

Defines the behaviour of publisher when auto-revalidation is enabled on the server and when PublishBehaviourInAutoRevalidation is set to Block. It signifies the time interval to sleep on each retry attempts i.e. the value specified in MaxBlockPublisherRetryAttempts.

### Valid value:

Time in milliseconds. The default value is set to 1 second.

## ClientProxyURL

ClientProxyURL parameter holds the configuration information of the client proxy provider for http tunneling.

### Valid value:

**String** - value that contains information about the proxy provider.

**Example:** http://ClientProxyServer:80

---

## CompressionManager

CompressionManager implementation is used for compressing messages. The Compression Manager specified is the implementation of the **fiorano.jms.services.msg.compression.ICompressionManager** interface provided by FioranoMQ.

### Valid value:

Class path of the implemented Compression Manager Set as the default value is:  
fiorano.jms.services.msg.compression.def.CompressionManagerImpl

## Connection ClientID

Connection ClientID is used for all the connections that are created using this connection factory.

### Valid value:

String value

### Dependencies:

This parameter depends on **EnsureUniquenessOfClientID** of **FioranoMQ->Fiorano->etc->FMQConfigLoader**. If **EnsureUniquenessOfClientID** is set to **true**, no two connections can have the same clientID. Setting the ConnectionClientID will throw exceptions when more than one connection is created with the Connection Factory.

## CreateLocalSocket

CreateLocalSocket parameter is used when both the Client and the Server share the same machine.

If set to true a socket is created when the client connects to the Server. If set to false no socket is created when local connections are made.

### Valid values:

- **yes** - creates a local socket.
- **no** - does not create a local socket. This is the default value.

Default Value: **no**

## Disable Ping

Disable Ping is the boolean value used to disable pinging for a particular client when pinging is enabled on the server.

---

If ping is enabled, the client will ping the Server for every **PING\_INTERVAL** seconds which are, by default, set to 60 seconds. If a reply is not received from the Server, the client will re-validate the connection.

**Valid values:**

- **yes** - ping is disabled on the client-side.
- **no** - ping is enabled on the client-side. This is the default value.
- **none** - the default value is used.

## DisableSendingCSPStoredMessages

DisableSendingCSPStoredMessages is the boolean value that is used to disable sending pending messages stored in the CSP to the Server.

When a connection with particular clientID is interrupted and if Durable Connections are enabled, messages will be stored in the local cache under the clientID of the connection. If this flag is enabled, these messages will not be sent in the setClientID () call.

**Valid values:**

- **true - yes** - disables sending messages stored in the CSP when the client ID is set.
- **False - no** - enables sending messages stored in the CSP when the client ID is not set.

**Note:** By default, **DisableSendingCSPStoredMessages** is set to **false** or **no**. Studio the possible values are **yes/no**. While setting using samples the values are **true/false**.

### JNDI name

FioranoJNDIContext.DONT\_SEND\_PREVIOUSLY\_STORED\_MESSAGE

Example: env.put(FioranoJNDIContext.DONT\_SEND\_PREVIOUSLY\_STORED\_MESSAGES, "true");

### Usage

This parameter is set when the messages stored in the CSP are NOT to be sent once a connection is re-established with the Server.

**Example:**

The Server is started with the durable connection enabled. A publisher and a subscriber are started. The publisher has the **DONT\_SEND\_PREVIOUSLY\_STORED\_MESSAGES** flag set to **true**. The server is shutdown. The publisher publishes a few messages and is shutdown as well. The server and the publisher are restarted. The subscriber does not receive the messages sent by the publisher while the Server was down.

## DurableConnectionReconnectInterval

DurableConnectionsReconnectInterval is the time interval between two re-connection attempts.

When a client is disconnected from the Server with auto revalidation enabled, the client repeatedly tries to reconnect to the Server in the form of a loop. The time between each successive try is set using this flag.

### Valid value:

This value is set in Milliseconds. The default time interval is 1000 milliseconds.

This parameter is used only when auto revalidation is enabled.

## DurableConnectionsBaseDir

When durable connections are enabled and the Server goes down, client-side messages are stored on the local disk while the connection is revalidated. The DurableConnectionsBaseDir parameter specifies the name of the base directory where messages will be persisted.

### Valid value:

Any string value that may be considered a directory name.

The default value is set to **cspCache**. Messages persist in the directory cspCache if no other variable is set.

## EnableAutoRevalidation

EnableAutoRevalidation is the boolean value that is used to disable auto-revalidation for a particular client.

By enabling auto revalidation a client attempts to reconnect to the Server when the Server is down.

### Valid value:

- **yes** - enables auto revalidation for the client. This is the default value.
- **no** - disables auto revalidation for the client.

The default value is set to **enabled**.

Revalidation occurs by the client only when auto revalidation is enabled on the Server. Revalidation by the client does not occur if auto revalidation is disabled on the Server and enabled in the Connection Factory parameter.

The Server value takes precedence over the Connection Factory parameter or the parameter set by the client.

---



## EnableLMS

EnableLMS is the boolean value that is used to enable/disable Large Message Support (LMS).

### Valid values:

- **yes** - enables LMS on the client-side. This is the default value.
- **no** - disables LMS on the client-side.

### Dependencies:

**UseFioranoCbr** flag should be set to **no** for LMS to work. LMS does not work if **AllowDurableConnections** is set to **TRUE**. LMS does not work in the case of HA.

## HTTPProxyURL

The HTTPProxyURL parameter holds the configuration information of the HTTP proxy provider.

### Valid value:

A String value containing information about the proxy provider:

Example: http://ProxyServer:80

## isThreadContextClassLoaderUsed

Sets the value of USE\_THREAD\_CONTEXT\_CLASS\_LOADER.

Valid values: **yes/no/none**

## java.naming.security.protocol

Java.naming.security.protocol is the name of the security protocol used to create secure connections with the FioranoMQ Server.

### Valid value:

The possible values that this variable can take are **PHAOS\_SSL** and **SUN\_SSL**.

## LookupPreferredServer

LookupPreferredServer is the boolean value that is used to instruct the client to connect to the preferred Server. When this parameter is enabled, clients connecting to the Dispatcher are redirected to the Server that is set as the preferred Server. If this parameter is disabled, clients will be connected to the least loaded Server.

### Valid values:

- **yes** - enables Lookup Preferred Server
-

- **no** - disables Lookup Preferred Server

**Dependencies:**

This parameter is used only by a Dispatcher Server.

## MaxAdminConnectionReconnectAttempts

The MaxAdminConnectionReconnectAttempts are the maximum number of reconnect attempts that will be made by the Admin Connection to connect to the Server when the Server is down.

**Valid value:**

Any positive integer value. By default, this parameter is set to -1. (Infinite attempts.)

**Note:**

- If a positive value is defined, the Admin Connection tries to reconnect that number of times.
- If a connection is not made within attempts defined, the attempted revalidations are terminated and an exception is thrown.

## MaxBlockPublisherRetryAttempts

Defines the behaviour of publisher when auto-revalidation is enabled on the server and when PublishBehaviourInAutoRevalidation is set to Block. It signifies the number of retry attempts to make when server is in transition state i.e STANDALONE state and then to ACTIVE TRANSITION to ACTIVE.

**Valid value:**

Any positive integer value. Default value is 10.

## MaxDurableConnectionReconnectAttempts

MaxDurableConnectionReconnectAttempts are the maximum number of reconnect attempts that the client will make if it is unable to connect to the Server when the Server is down.

**Valid value:**

Any positive integer value. By default, this parameter is set to -1. (Infinite attempts.)

**Note:**

- This flag will be used only if durable connections are enabled on the Server.
  - If a positive value is defined, the connection tries to reconnect that number of times.
  - If a connection is not made within attempts defined, the attempted revalidations are terminated and an exception is thrown.
-

## MaxSocketCreationTries

MaxSocketCreationTries are the maximum number of attempts that the client will make to create a socket connection on a Server when it is unable to connect to the Server. If it fails to connect within the specified number of attempts an exception is thrown on the client-side.

### Valid value:

Any positive integer value. By default, this value is 1.

## ProxyAuthenticationRealm

ProxyAuthenticationRealm holds the address of the Authentication Realm being used on the proxy Server through which HTTP based connections created using the ConnectionFactory are routed.

### Valid value:

String representing the address of the proxy Server on which the Authentication Realm exists.

### Dependencies:

This property is used only when the Transport Protocol is set to HTTP.

## ProxyCredentials

ProxyCredentials is the password of the proxy principal which is used when the proxy Server is used.

## ProxyPrincipal

ProxyPrincipal is the name of the proxy principal used when the proxy is used.

## ProxyType

Sets the type (name) of the proxy being used for the HTTP based connections created using the ConnectionFactory. This property is used only when the Transport Protocol is set to HTTP.

### Valid values:

- MS\_ISA\_PROXY
  - WIN\_PROXY
  - NETSCAPE\_PROXY
  - WINGATE\_PROXY
  - DEFAULT\_PROXY
-

## PublishBehaviourInAutoRevalidation

PublishBehaviourInAutoRevalidation parameter defines the behavior of the publisher when the auto revalidation is enabled and the durable connections are disabled in the Server. A new publish call will either throw an exception, or block or ignore a message. By default the value of this parameter is - **throw exception**.

### Valid values:

- **0 – Exception** - Throws an exception upon publishing messages. This happens when the Server is down, auto revalidation is enabled but durable connections are disabled.
- **1 - Ignore** - Ignores further publish message calls. All messages sent when the server is not up will be lost. (The same conditions as above.)
- **2 – Block** - Blocks further messages from being published until auto revalidation is performed. (The same conditions as above.)

### JNDI name:

FioranoJNDIContext.PUBLISH\_BEHAVIOUR\_IN\_AUTO\_REVALIDATION

Example, env.put(FioranoJNDIContext.PUBLISH\_BEHAVIOUR\_IN\_AUTO\_REVALIDATION, "2");

### Usage:

This parameter is used to prevent exceptions from being thrown when messages are sent during auto revalidation undertaken when durable connections disabled. The User may either choose to ignore the messages sent till auto revalidation is done or the User may prevent sending messages till auto revalidation is complete.

### Example:

If the FioranoMQ Server is used for real-time trading, old messages cannot be used. If the Server is down the publisher should not send any messages as these will be sent once the Server is up and running. The flag should, therefore, be set to **2** which blocks the publisher from sending messages when connection with the server is down.

### Dependencies:

If these parameters are present in the client then **EnableAutoRevalidation** must be set to **true** and **AllowDurableConnections** must be set to **false**.

## PublishWaitDuringCSPSyncup

When the Server is disconnected, messages are stored in the CSP on the local machine. When the Server is reconnected, messages stored in the CSP are sent to the Server while current messages are being stored in the CSP with some **wait-time**. The publish call waits for **CSPSyncup** time specified by the PublishWaitDuringCSPSyncup parameter until the CSP messages are sent to the Server. After all CSP messages are sent, the publisher sends messages normally without any delay time.

---

**Valid value:**

Time is specified in milliseconds. The default value is 1000 milliseconds.

## SecurityManager

The SecurityManager implementation is used to create secure connections [HTTPS or SSL] with the FioranoMQ Server. This manager should be an implementation of the **fiorano.jms.runtime.IFMQSecurityManager** interface provided by FioranoMQ.

**Valid value:**

Class path to the security Manager class.

## ServerProxyURL

The ServerProxyURL parameter holds the URL for the Server proxy through which TCP based Connections will be routed using HTTP Tunneling.

**Valid value:**

String value that contains information about the proxy provider.

Example: http://ClientProxyServer:80

**Dependencies:**

This URL will be used only when the Transport Protocol is set to TCP.

## SleepBetweenSocketCreationTries

SleepBetweenSocketCreationTries is the time interval between two socket creation attempts. While creating a connection to the server, client RTL creates sockets on the Server. If the Server is unavailable at that time, RTL tries to create a socket for as many times as specified in the parameter – **MaxSocketCreationTries**. Between successive tries the RTL waits for the time specified in this parameter.

**Valid value:**

Time is specified in milliseconds. The default sleep time is 200 milliseconds.

## SocketKeepAliveEnabled

Once the property is set to true, packets are sent to the remote system when no data is being exchanged to keep the connection active. This is handled by the TCP layer itself.

By default, this value is **off**.

---

## SocketTimeout

SocketTimeout is the time interval after which the socket calls a **timeout**. Timeout is when the flow of execution is stopped if still awaiting a reply from the socket. If the connection to the Server is lost, applications hang onto the socket for the maximum time set by this parameter.

### Valid value:

Time is specified in milliseconds. The default timeout value is set to four minutes.

## SocksProxyURL

Sets the URL for the SOCKS Proxy through which HTTP based connections are routed.

### Dependencies:

This URL will be used only when the Transport Protocol is set to HTTP.

## TCPBatchSize

Non-persistent messages are sent to the Server in batches. The TCPBatchSize parameter determines the size of the batch. If the message batch size exceeds the size determined, the batch is sent to the Server or the messages are stored in a buffer.

### Valid value:

The size is specified in bytes. The default value is 32KB

### Dependencies:

Batching should be enabled if this parameter is to be used. If BatchTimeoutInterval completes before the message batch size, then messages are sent to the Server irrespective of the batch size.

## TransportProtocol

Protocol used for communicating with the Server.

### Valid value:

Transport protocol can be set to either **TCP** or **HTTP**.

## UseFioranoCbr

The UseFioranoCbr parameter enables/disables Content Based Routing (CBR). CBR allows XPath based selection on messages with XML content. For more information please refer to chapter 18: FioranoMQ Content Based Routing available in the FioranoMQ Concept Guide.

---

**Valid value:**

- **yes** - enables Fiorano CBR.
- **no** - disables FioranoCBR.

## UpdateConnectURL

UpdateConnectURL is the boolean value that is used to specify whether a 'connect URL' of the connection factory should be updated when the Server restarts.

**Valid values:**

- **yes** - updates the connectURL
- **no** - does not update the connectURL

By default this value is **false**.

## UseLocalProcedureCalls

UseLocalProcedureCalls is the boolean value used to enable/disable Local Procedure Calls (LPC). If this parameter is enabled then clients within the server using the Connection Factory will connect to the Server directly, without making any socket connections.

**Valid values:**

- **yes** - enables LPC.
- **no** - disables LPC. This is the default value. .

By default, LPC is **disabled**.

## UseSingleSocketForSendReceive

By default, FioranoMQ uses two sockets per connection. One socket is used for sending requests and another for receiving messages. This property allows the User to use the same socket for, both, send and receive operations.

**Valid values:**

- **yes** - uses a single socket for send and receive.
- **no** - uses two socket for send and receive.

By default, this is **true**.

## XASocketTimeout

Time interval after which the socket call will **timeout** in the XA enabled Server.

---

**Valid value:**

Time is specified in milliseconds. The default timeout value is set to ten minutes.



# Chapter 2: Common FioranoMQ Configuration

---

This chapter explains the parameters that can be configured at the FioranoMQ Server level. These parameters are commonly used across the FioranoMQ Server and can be configured in the default profile at the node FioranoMQ->Fiorano->etc->FMQConfigLoader in Offline Configuration mode using Studio.

For information on how to configure the FioranoMQ Server in Offline mode, refer to **Chapter 3 Offline Configuration Through Profile Manager** and for Online Configuration (through the Web Management Console), refer to **Chapter 30 FioranoMQ Web Management Console** of *FioranoMQ Handbook*.

## FMQConfigLoader

This chapter explains the parameters present in **FioranoMQ->Fiorano->etc->FMQConfigLoader**

### AcIBasedDestinationSecurity

This indicates whether ACL based security is enabled.

#### Valid values:

The default value is **no**.

- **yes** - if enabled, User operations will first be checked against the associated ACL.
- **no** - if disabled, User operations will not be checked against the associated ACL.

#### Example:

In a multi user environment in which each User must have different access privileges to the FioranoMQ Server, this value must be set to **yes**.

### AllowDurableConnections

A Durable Connection maintains connectivity with FioranoMQ at all times. Applications do not have to take care of storing, re-connecting and then forwarding stored messages to the Server. These activities are not visible to the client application and are automatically performed by FioranoMQ's runtime library. When the connection is restored, messages stored in the local store are automatically sent to the server.

#### Valid values:

The default value is **no**.

---

- **yes** - durable connections are enabled in the Server. All that a client application has to do to make its connection durable is to **AllowDurableConnections** in its application code. Please refer to Section 5.1.1. in the FioranoMQ Handbook.
- **no** - durable connections are not enabled in the Server. This **nullifies** the **AllowDurationConnections** property set in the client.

#### Example:

Consider a process computer monitoring a steel mill. Real-time steel production information is sent each second to a main hub. The main hub uses this information to generate the desired results. If the connection between the Process machine and the Hub breaks, the send mechanism fails and an exception is raised. Since this data is generated only once, the application requires to store this data upon encountering the exception and while trying to connect to the server. This adds considerable load to the application. In such cases, a Durable Connection comes to the rescue by doing the work for the application. It automatically tries to reestablish the connections, stores the data in transit and sends it to the Server as soon as the connection is restored.

#### Dependencies:

**AutoRevalidationEnabled** - If **AllowDurableConnections** is set to **yes**, **AutoRevalidationEnabled** will automatically be set to **yes**.

### AllPermissions

This parameter determines whether all default permissions for a new ACL should be negative or positive. For this option to have an effect **AclBasedDestinationSecurity** must be set to **true**.

#### Valid values:

The default value is **yes**.

- **yes** - when set to yes, all default permissions for a new ACL would be positive.
- **no** - when set to no, all default permissions for a new ACL would be negative.

#### Example:

This parameter can be set to **no** when Users are to be added with their respective permissions added later.

### AllowOnTheFlyAclCheck

This flag indicates whether modifications in an ACL would be reflected on clients while the Server is running. If **AclBasedDestinationSecurity** is set to **yes**, this will not affect those clients that are connected unless **AllowOnTheFlyAclCheck** is set to **yes** as well.

**Valid values:**

The default value is **no**.

- **yes** - clients that are connected behave similar to future clients that are to connect to the Server after modifications to the ACL.
- **no** - C clients that are connected to the Server behave as they did prior to the modifications to the ACL.

**Dependencies**

1. The **AllowOnFlyAclCheck** flag works for all permissions except in the instance below where: A publisher is publishing non-persistent messages on a topic.
2. The permission to create a publisher is revoked on this topic.
3. No exception is thrown even though the User is not allowed to publish because messages are sent in batch mode. Therefore, to receive an exception:

**Solution One:**

For NP messages, batching are enabled by default which leads to the behavior mentioned above. To receive an exception at the send API, set the **BatchingEnabled** parameter in the **ConnectionFactory** to FALSE.

**Solution Two:**

Add the line below in the client code environment while performing the lookup function:

```
env.put("BatchingEnabled", "false")
```

**Note:** `env` is the environment passed while performing a JNDI lookup. This disables batching for that particular client.

**See:** `AclBasedDestinationSecurity`.

## AllowOnTheFlyCreationOfDestinations

This flag controls the behavior of `createTopic` and `createQueue` APIS in a JMS Session. This deters a User from creating the destination using the `session.createTopic` or `session.createQueue` APIS. This does not prevent the admin User from creating destinations. Destinations can still be created using admin connection and admin services.

**Valid values:**

The default value is **yes**.

- **yes** - a new destination is automatically created when a destination name that does not exist is invoked.
- **no** - when a destination name that does not exist is invoked an exception will be thrown.

**Example:**

When clients are not be allowed to create destinations, the FioranoMQ Server administrator can make sure only the required destinations are created and clients do not add to existing destinations by setting this value to **no**.

---

## CreateDefaultACL

This indicates whether to create default ACLs for different FioranoMQ objects. When set to **yes** different FioranoMQ objects are attached with their respective ACLs that decide which set of users/groups have access to a particular FioranoMQ object.

### Valid values:

The default value is **yes**

- **yes** - FioranoMQ objects have their respective default ACLs. For default ACLs to have an effect, **AclBasedDestinationSecurity** must be set to true.
- **no** - no default ACLs are created for FioranoMQ objects.

See also AclBasedDestinationSecurity.

## EnableAutoRevalidation

EnableAutoRevalidation enables controlling auto revalidation. Auto revalidation refers to Fiorano runtime's ability to detect a loss of connection and its subsequent attempts to automatically re-connect back to the server.

### Valid values:

The default value is **no**.

- **yes** - Fiorano runtime will automatically try to reconnect to the server on detecting a loss of connectivity.
- **no** - the client will not reconnect automatically upon loss of connection.

### Dependencies

The parameter above depends on **AllowDurableConnections**. If **EnableAutoRevalidation** is set to **yes** then **EnableAutoRevalidation** is also set to **yes**.

## EnsureUniquenessOfClientId

Every FioranoMQ JMS client is supplied with a clientId. This flag indicates whether uniqueness of clientIDs is required.

### Valid values:

The default value is **yes**.

- **yes** - a connection that sets a client ID set on another connection will get an exception upon doing so.
- **no** - a connection that sets a client ID set on another connection will proceed normally.

### Example:

When each clientId is required to be unique, this value must be set to **yes**.

---

## HttpPollingInterval

The polling interval for HTTP requests the amount of time in milliseconds. The request waits for messages before returning a response from the Server.

### Valid values:

The default value is **10000**.

Range of integer values in java are:  $-2^{31}$  to  $2^{31} - 1$ .

All values less than or equal to 0 are equal to each other.

## IncludeMessageID

IncludeMessageID determines whether to include the messageID as part of the message.

### Valid values:

The default value is **no**.

- **yes** - messageID will be included as part of the message.
- **no** - messageID will not be included as part of the message.

## LazyRSCreation

LazyRSCreation is a value that determines if the thread creation is optimized on the client-side. Although the connection is started with the start method call, a thread for listening in on the data has to be started. When the thread creation is optimized, a thread is created when the first consumer joins a session created by the connection.

### Valid values:

- **yes** – the thread creation is optimized on the client-side. A thread is created when the first consumer joins a session created by the connection.
- **no** – the thread is not optimized. A thread is created as soon as the connection is started. This is the default value.

### Example:

When the number of threads running in an application need to be economized, the value must be set to **yes** so that there are no unnecessary threads created until a consumer joins a session.

## MaxTransactionBufferSize

MaximumTransactionBufferSize is the maximum amount of data (in bytes) that a transacted Session would store in an uncommitted state. Any attempt to publish more data in an uncommitted transaction will result in an exception.

---

**Valid values:**

The default value is **10240000**

**Range** of integer values in java. ( $-2^{31}$  to  $2^{31} - 1$ )

All values less than zero are equal to each other.

### MessageSelectorFactoryClassName

MessageSelectFactoryClassName is the class name that provides the Content Based Routing (CBR) Engine functionality for FioranoMQ Server. This property is used only if CBR is enabled in the FioranoMQ Server.

**Valid values:**

The default value is **fiorano.jms.cbr.cbr1.def.MessageSelectorFactory**.

### PingEnabled

PingEnabled property controls client connections pinged automatically. Pinging is essential for detecting Network problems.

**Valid values:**

The default value is **yes**.

- **yes** - client connections are pinged automatically.
- **no** - client connections are not pinged automatically.

### ResumeTimeoutInterval

ResumeTimeoutInterval is the integer specifying the resume timeout to be used by a Large Message Support(LMS) application. If timeout is not resumed within the given period, resuming timeout is stopped. For more details about LMS, please refer to Chapter 8 in FioranoMQ Handbook.

**Valid values:**

The default value is -1. (This indicates that the application will wait indefinitely.)

Range of long values in java -  $-2^{63}$  to  $2^{63} - 1$ .

All values less than zero are equal to each other.

### SSLEnabled

SSLEnabled is the property which enables a SSL connection with the Server.

---

**Valid values:**

The default value is **no**.

- **yes** - SSL connections are enabled with the server.
- **no** - SSL connections are not enabled with the server.

## SystemEncodingFormat

SystemEncodingFormat encoding format for UTF.

**Valid values:**

Any string.

The default value is **UTF-8**.

## UseFioranoCbr

In group based systems, messages are classified as belonging to a certain group referred to as a 'topic'. Publishers are required to label each message with a topic name, while consumers subscribe to all messages on a particular topic.

When set to **yes** this offers a better alternative to group-based systems, known as content-based routing. These systems route messages to subscribers based on content instead of message properties contained in the headers. There is no overhead imposed on the publisher and prior knowledge of the domain is not required. Subscribers have the added flexibility of choosing filtering criterion along multiple dimensions, without requiring a pre-definition of groups.

**Valid values:**

The default value is **no**.

- **yes** - enables content based routing at the Server-side. The Server will now have CBR enabled, and clients can send and receive XML messages with XPath selectors. FioranoMQ. CBR utilizes a subset of XPath notation and SQL92 syntax to specify XPath message selectors. Only absolute paths are to be used. Several XPath strings can be combined with AND/OR conditions. Please refer to samples/PubSub/ContentBasedRouting for running clients with CBR.
- **no** - content based routing is not enabled in the Server.

**Example:**

Stock Trade Example

Consider a brokerage firm that can have thousands of subscribers interested in information on stock trades. Each subscriber has their own selection criterion based on individual requirements. One subscriber would like to be alerted when two stocks fall below a certain price.

MSFT stock falls below 55 AND ORCL stock falls below 15.

---

## UseSingleSocket

Each JMS Connection results in the creation of two sockets with the Server. By turning on this flag each Fiorano client is instructed to use a single socket rather than both sockets.

### Valid values:

The default value is **no**.

- **yes** - each JMSConnection that a client makes results in one socket.
- **no** - each JMSConnection that a client makes results in two sockets.

### Example:

Where sockets are to be economized, set this value to **yes**.

## UseSingleSocketForAdmin

Turning on this flag, will result in starting off a thread for Admin Connection that waits for data on a socket, constantly. This enables the detection of a loss of connection immediately.

### Valid values:

The default value is **yes**.

- **yes** - a thread for an Admin Connection is created on the socket and it waits for data on socket, constantly. This enables the detection of a loss of connection immediately.
- **no** - loss of connection will not be detected immediately.

### Example:

In most situations it is better to set **UseSingleSocketForAdmin** to **yes** because it provides an easy way to immediately detect a loss of connection.

---



# Chapter 3: Queue Subsystem Level Configurations

---

This chapter explains the parameters that can be configured for JMS storage objects of type 'Queue'. In general, these parameters are the most common ones used in the Point-to-Point (PTP) model of JMS and they can be configured in the default profile at the node FioranoMQ->Fiorano->mq->ptp->QueueingSubsystem through Offline configuration using Studio.

For information on how to configure the FioranoMQ Server in Offline mode, refer to **Chapter 3 Offline Configuration Through Profile Manager** and for Online Configuration (through the Web Management Console), refer to **Chapter 30 FioranoMQ Web Management Console** of *FioranoMQ Handbook*.

**Note:** From FioranoMQ 9.1.0 release onwards, a unique Destination Level Configuration support is included. For more on this, please refer to section **29.1 Support for Destination Level Configuration** in the *FioranoMQ Handbook*.

## UnAckedQueueBufferSize

UnAckedQueueBufferSize is the buffer size of the receiver queue for unAcked messages. Where the size of the message queue for unAcked messages exceeds this buffer limit, the client gets a message to commit the received messages.

### Values:

The default value set for this parameter is **10485760** bytes. Any positive integer can be assigned as a value for this parameter.

## MaxNumberOfQueues

MaxNumberOfQueues are the maximum number of queues that can be created. This includes Temporary Queues. The JMS provider allows the creation of queues upto the number of queues specified here. Attempts to create queues beyond the number of queues specified here will be.

### Values:

The default value set for this parameter is **-1**. This suggests that infinite queues may be created. Positive integers or -1 may be assigned to this parameter.

## RedeliveryTriesOnListenerException

RedeliveryTriesOnListenerException parameter specifies the number of redelivery tries when RuntimeException is thrown in the Message Listener. This is used in AUTO\_ACKNOWLEDGE or DUPS\_OK\_ACKNOWLEDGE mode only. The redelivered message is discarded once this value is reached.

---

**Values:**

The default value set for this parameter is **2**. Any positive **integer** may be assigned to this parameter. If this parameter is given a negative value, the message will not be delivered to the consumer.

**Example:**

Where there is a `RuntimeException` thrown while processing the message received by the `MessageListener`, it is ensured that the message gets redelivered before the number of attempts reaches this maximum limit specified. (This makes it compliant with JMS specifications.)

**Dependencies:**

Dependencies are occur only when the client session is either in **AUTO\_ACK** or **DUPS\_OK\_ACKNOWLEDGE** modes.

### DelayInMsgDeliveryOnListenerException

`DelayInMsgDeliveryOnListenerException` parameter specifies the delay in message redelivery when `RuntimeException` is thrown in Message Listener. This is used in **AUTO\_ACKNOWLEDGE** or **DUPS\_OK\_ACKNOWLEDGE** mode only. The redelivered message is discarded once the maximum redelivery tries value that is specified is reached.

**Values:**

The default value for this parameter is **-1**. This indicates that there is no delay between the tries at redelivery of a message when `RuntimeException` occurs in the `MessageListener`. Any positive value can be assigned to this parameter. There will not be any delay between attempts if a negative value is assigned to this parameter.

**Dependencies:**

### Dependencies occur only in when the client session is either in AUTO\_ACK or DUPS\_OK\_ACKNOWLEDGE modes.CleanupDmqAtStartup

`CleanupDmqAtStartup` enables the cleanup of the **DeadMessageQueue** at the startup of the Server. If this flag is set to **true** prior to the startup of the Server all messages from the **SYSTEM\_DEADMESSAGES\_QUEUE** will be purged.

**Values:**

The default value for this parameter is **false**. Valid values for this parameter are **true/false**.

Restart of server required: TRUE

---

## EnableSnooperOnAllQueues

EnableSnooperOnAllQueues specifies whether the snooper service is enabled on all queues. When snooping is enabled on a queue all messages that are sent to the queue are copied to a topic named **SYSTEM\_MESSAGESNOOPER\_QUEUE**. This insures that any subscribers registered on this topic can snoop the messages sent to that particular queue.

### Values:

The default value for this parameter is **false**. The valid values for this parameter are **true/false**. When set to **true** a **SnooperListener** is added to each one of the queues and all the incoming messages are snooped prior to being added to the topic **SYSTEM\_MESSAGESNOOPER\_QUEUE**.

### Example:

This parameter can be used when it is necessary to monitor messages being sent to the queues by the clients. To monitor messages that are being sent to queues enable this parameter and subscribe to the topic **SYSTEM\_MESSAGESNOOPER\_QUEUE**.

Restart of server required: FALSE

## EnableDMQOnAllQueues

EnableDMQOnAllQueues specifies whether the DMQ service is enabled on all queues. When the DMQ service is enabled on a queue all expired messages that need to be stored are stored in the **SYSTEM\_DEADMESSAGES\_QUEUE** by default.

### Values:

The default value for this parameter is **false**. Valid values for this parameter are **true/false**.

### Example:

This parameter can be used when it is necessary to monitor messages that have expired.

### Dependencies:

The expired messages are stored only when the **StoreWhenDead** flag, set for **FioranoMessage**, is set to **true**. The 'getter' and 'setter' methods for this flag are **getStoreWhenDead** and **setStoreWhenDead** respectively.

Restart of server required: FALSE

---

## PrefetchCount

PrefetchCount specifies the prefetch count for single receive calls. Prefetch count is the number of messages fetched in a single receive call. It denotes the maximum number of messages that are fetched from the Server in one single received call. The number of messages fetched also depends on the parameter **MaxPrefetchSize**. If the total size of the batch of messages exceeds the **MaxPrefetchSize** then the number of messages fetched may be less than the **PrefetchCount** set.

### Values:

The default value of this parameter is **thirty**. Valid values are any positive integer values greater than or equal to the **PrefetchThreshold** value specified.

### Dependencies:

If the message count to be delivered to the consumers approaches the **PrefetchThreshold**, then only the client can send a request to fetch the number of messages set by **PrefetchCount** value from the Server.

## PrefetchThreshold

PrefetchThreshold is the message count used for a single receive call. When the number of messages in the message queue of the client approaches this limit the client sends a request to the Server to fetching more messages. The number of fetched messages depends upon the value of the **PrefetchCount**.

### Values:

The default for this parameter is **1**. Valid values for this parameter are any positive integer values less than the value of the PrefetchCount.

### Dependencies:

If the message count approaches the **PrefetchThreshold**, only the client can send a request to fetch the number of messages set by the value of the PrefetchCount from the Server.

## DefaultStorageTypeForQueues

DefaultStorageTypeForQueues string specifies the default storage type of the data related to all queues that may be used by the application.

### Values:

The default value for this parameter is **File**. Valid values for this parameter are **File/RDBMS**. If this parameter is set to **File** all data about the queues is stored in the File Based Storage and the value of this parameter is set to **RDBMS**. All relating data about the queues is stored in RDBMS sbased Storage.

---

**Dependencies:**

If this value is set to **RDBMS**, then the parameter **EnableRDBMS** should be set to **true**. if this value is set to **File**, then the parameter **EnableRDBMS** should be set to **false**.

## MaxPrefetchSize

MaxPrefetchSize specifies the maximum prefetched size of fetched messages in one receive call. It denotes the maximum size of the batch of messages that can be fetched from the Server.

**Values:**

The default value of this parameter is 264144 bytes, equivalent to 256KB. Valid values of this parameter include all positive integers.

**Example:**

If all the parameters are set to the default values and if the size of each message is 100KB then, at most, three messages can be fetched from the Server. This is because the total batch size exceeds the **MaxPrefetchSize** which is 256KB.

## OverflowFromBottomEnabled

OverflowFromBottomEnabled concerns the overflow of non-persistent messages. This parameter determines whether messages are to be dropped from the bottom of the queue.

**Values:**

- Default value: False
- Valid values: True/False

## DMQExpiryTime

DMQExpiryTime is the time measured in milliseconds after which any stored messages in the **Dead Message Queue** is deleted. If this value is set to a positive integer, a timer is registered which cleans up the **SYSTEM\_DEADMESSAGES\_QUEUE** at regular intervals.

**Values:**

The default value for this parameter is **0** milliseconds. Valid values for this parameter include all positive integer values which falls in the **Long** range.

---

## Restart of server required: TRUEEnableNotificationOnDeadMessage

EnableNotificationOnDeadMessages enables notification of DeadMessage. , When an expired message from a queue reaches the **SYSTEM\_DEADMESSAGES\_QUEUE** for storage, if this parameter is set to **true** an event will be raised.

### Values:

The default value for this parameter is **false**. Valid values for this parameter are **true/false**.

### Dependencies:

The DMQ should be enabled for the queue on which the message was originally sent. Only if the DMQ is enabled will the message be sent to the **SYSTEM\_DEADMESSAGES\_QUEUE** on expiry. Event notification will be activated only if the **NotifyWhenDead** flag for FioranoMessages is set to **true**. The 'getter' and 'setter' methods for this flag are **getNotifyWhenDead** and **setNotifyWhenDead** respectively.

## Restart of server required: FALSEEnableMessageMonitoring

EnablingMessageMonitoring enables the monitoring of messages and stores this data. This parameter takes a maximum of five seconds to be enabled.

### Values:

The default value for this parameter is **false**. Valid values that can be assigned to this parameter are **true/false**.

## FilePath

FilePath returns the file path set to store data acquired through monitoring of Server messages.

### Values:

The default value for this parameter is  
**%FIORANO\_HOME%\fmq\profiles\FioranoMQ\run\PTP\JMSX\_MESSAGEMONITOR.**  
Any valid file path can be assigned to this parameter.

### Dependencies:

To store server message data, the **EnableMessageMonitoring** flag should be set to **true**.

## TimeDuration

TimeDuration returns the **time duration** of messages received in seconds to enable monitoring message flow. The value for this parameter should be more than five seconds. This time duration is used to calculate the InBound and OutBound message rate (at the time the Server message data is being monitored).

---

**Values:**

The default value for this parameter is **3600** seconds. Valid values for this parameter include any positive integer values greater than five.

## CleanupInterval

CleanupInterval specifies the interval after which the **QueueCleaner** utility cleans the messages from the queue. This parameter is useful only if **IsDbCleanupEnabled** is set to **true**.

**Values:**

- Default value: 60000
- Valid values: Any positive value in the **long** range.

**Example:**

When deleting expired messages from the queue the TimeDuration parameter is used. After the specified period of time the queue gets cleaned of all expired messages.

Restart of server required: TRUE

## InMemoryBlockingInterval

InMemoryBlockingInterval is the blocking interval that pushes a message into the **QueueBuffer** if the queue is full.

**Values:**

- Default value: 10
- Valid values: Any positive value in the **long** range.

**Example:**

Blocks sender for the specified amount of time if the QueueBuffer is full.

Restart of server required: FALSE

## InMemoryBufferSize

InMemoryBufferSize specifies the buffer size of the InMemory Cache. If the InMemoryBuffer is full, then reattempts to push the message will take place based on the value of the parameter **MaxPushAttempts**.. The wait interval is set using the parameter **WaitBetweenAttempts**.

**Values:**

- Default value: 1048576
  - Valid values: Any positive value in **long** range
-

Restart of server required: FALSE

## PersistentInMemoryBufferSize

PersistentInMemoryBufferSize specifies the buffer size of the InMemory Cache of persistent messages. If the PersistentInMemoryBuffer is full, then reattempts to push the message will take place based on the value of the parameter **MaxPushAttempts**. The wait interval is set using the parameter **WaitBetweenAttempts**.

### Values:

- Default value: 524288
- Valid values: Any positive integer in the **long** range.

Restart of server required: FALSE

## MaxPushAttempts

MaxPushAttempts is the maximum number of attempts for pushing InMemoryBuffer. This parameter is particularly useful when the InMemoryBuffer is full. A maximum number of attempts to push the message to InMemoryBuffer are allocated.

### Values:

- Default value: 64
- Valid values: Any positive integer value.

Restart of server required: FALSE

## WaitBetweenAttempts

WaitBetweenAttempts specifies the wait time between attempts at pushing messages into a queue. This parameter is particularly useful when pushing incoming message is not successful in the first attempt. This parameter determines the amount of wait time before another attempt to push the message into InMemoryBuffer is undertaken.

### Values:

- Default value: 16 (in milliseconds)
- Valid values: Any positive value in long range.

Restart of server required: FALSE

## IsDbCleanupEnabled

IsDbCleanupEnabled specifies whether the queue cleaner utility is enabled or not

---



**Values:**

- Default value: False
- Valid values: True/False

Restart of server required: TRUE

## UseInMemStatusCache

UseInMemStatusCache is the status Cache for messages.

**Values:**

- Default value: True
- Valid values: True/False

True - Uses InMemoryCache to store the status of the messages in DB (Deleted/Rolledback/Delivered and so on.)

Restart of server required: TRUE

## LoadBitSetOnStartup

LoadBitSetOnStartup loads the InMemory message index status **BitSet** on startup.

**Values:**

- Default value: False
- Valid values: True/False

Restart of server required: TRUE

## EnableGMSQueueExpose

EnableGMSQueueExpose is a boolean value that exposes the **QueueAttributes** at runtime on the **GMS** queue. If set to **true**, a runtime MBean relating to the **GMS** queue is exposed.

**Values:**

- Default value: False
- Valid values: True/False

Restart of server required: TRUE

## Exclusive

Boolean indicates about the sharing of cache tables. If set to **true**, exclusive cache tables are created for each queue. Non-exclusive cache tables are not supported in FioranoMQ.

---

**Values:**

- Default value: True
- Valid values: True/False

## JumpDeletedFiles

JumpDeletedFiles is a boolean value specifying whether the deleted table files may be jumped. If this flag is used it jumps the deleted cache table of files to the next undeleted message in the DB.

**Values:**

- Default value: False
- Valid values: True/False

Restart of server required: TRUE

## DepthMonitoringEnabled

DepthMonitoringEnabled turns on or turns off depth (the number of pending messages) monitoring count at the Server level. If this flag is set to **true**, depth monitoring is enabled at the Server level. Based on the depth monitoring flag at queue level, depth monitoring is enabled or disabled for that particular queue. If this flag is set to **false**, depth monitoring won't work for any queue irrespective of whether this flag is set at the queue level.

**Behavior at server level:**

If this value is set to **no** at the Server level, queue depth monitoring is stopped and notifications are terminated. If this value is set to **yes** at Server level, queue depth monitoring is enabled or disabled based on the configuration of this property at the queue level.

**Behavior at destination level:**

This property will come into effect only if the queue depth monitoring is enabled at the Server level.

**Values:**

- Queue Subsystem level (Server level): no
- Destination level: no

Restart of server required: FALSE

## DepthMonitoringLevels

Jmx notifications are fired when pending message count crosses one of the depth values specified. All thresholds should be specified as positive values with each of them separated by a comma, for example: '10,20,30'. The value specified will be used for all destinations unless explicitly stated that it is for a particular destination.

---

**Behavior at server level:**

Depth levels specified will be used only if the value for the property at queue level is **null**.

**Behavior at destination level:**

Depth levels specified here will override the value for levels specified at the Server level.

**Values:**

- Server level: null
- Destination level: null

Restart of server required: FALSE

# Chapter 4: Queue Level Configurations

---

This chapter explains the parameters that can be configured for JMS storage objects of type 'Queue'. In general, these parameters are the most common ones used in the Point-to-Point (PTP) model of JMS and they can be configured in the default profile at the node FioranoMQ->Fiorano->mq->ptp->Queues->specific queue through Offline configuration using Studio.

For information on how to configure the FioranoMQ Server in Offline mode, refer to **Chapter 3 Offline Configuration Through Profile Manager** and for Online Configuration (through the Web Management Console), refer to **Chapter 30 FioranoMQ Web Management Console** of *FioranoMQ Handbook*.

---

**Note:** From FioranoMQ 9.1.0 release onwards, a unique Destination Level Configuration support is included. For more on this, please refer to section **29.1 Support for Destination Level Configuration** in the *FioranoMQ Handbook*

## EnableJournaling

EnableJournaling specifies whether Journaling Service is enabled on this Queue.

### Values:

The default value for this parameter is **false**. Valid values for this parameter are **true/false**.

Restart of server required: FALSE

## StoreNPMessagesInDb

StoreNPMessagesInDb determines if non persistent message are to be stored in Data storage.

### Values:

The default value for this parameter is **false**. Valid values for this parameter are **true/false**.

Restart of server required: TRUE

## QueueLimitReachedNotificationThreshold

QueueLimitReachedNotificationThreshold is the threshold for number of messages residing in the queue beyond which JMX Notification will be fired It will be ignored if it's value is less than 1.

### Values:

The default value for this parameter is 0 milliseconds. Valid values for this parameter include all positive integer values which falls in the Long range.

---

Restart of server required: TRUE

### QueueBehaviorOnBufferOverflow

QueueBehaviorOnBufferOverflow determines the Queue behavior for the incoming messages when the size of the in-memory buffer used for storing NON\_PERSISTENT messages reaches its maximum limit.

#### Values:

The default value for this parameter is **default**. Legal values for this parameter are **DEFAULT,DropOldestMessage,Exception,WriteToDisk**.

Restart of server required: TRUE

### ForcePushWait

ForcePushWait specifies the wait-time if in-memory buffer is full during force push.

#### Values:

The default value for this parameter is 1. Any positive integer can be assigned as a value for this parameter.

Restart of server required: FALSE

### QueueIdleStateNotifierThresholdTime

Notifications will be sent if queue is idle for the time interval specified by this parameter.

#### Values:

The default value for this parameter is **0**. Valid values for this parameter include all positive integer values which falls in the Long range.

Restart of server required: FALSE

Remaining Queue parameters are mentioned in **Chapter3: Queue Subsystem Level Configurations**

This chapter explains the parameters that can be configured for JMS storage objects of type 'Topic'. In general, these parameters are the most common ones used in the Publish-Subscribe (PubSub) model of JMS and they can be configured in the default profile at the node FioranoMQ->Fiorano->mq->pubsub->TopicSubsystem through Offline configuration using Studio.

For information on how to configure the FioranoMQ Server in Offline mode, refer to **Chapter 3 Offline Configuration Through Profile Manager** and for Online Configuration (through the Web Management Console), refer to **Chapter 30 FioranoMQ Web Management Console** of *FioranoMQ Handbook*.

**Note:** FioranoMQ 9.1.0 onwards includes the Destination Level Configuration support. For more on this, please refer to section **29.1 Support for Destination Level Configuration** in the *FioranoMQ Handbook*.

### DupsOkBatchSize

The DupsOkBatchSize parameter indicates the number of messages received by a consumer for each consumer acknowledgement. A User specifies the number of messages after which client sends an acknowledgement to the server. This command will run only when the client application is accepting messages and the acknowledgement mode is DUPS\_OK. The acknowledgement mode is specified when creating a session. (See JMS specifications for details on how to create a session.)

#### Values:

The default value for the parameter DupsOkBatchSize is 20. Any positive integer may be used. Negative values so not throw an exception. Therefore it is important to check that positive integers have been given.

#### Example:

This mode is used when duplicate messages are accepted. There is a possibility of duplicate messages being delivered when the Server is down or the Client is not available.

#### Dependencies:

This flag is dependent on the consumer session **acknowledgment** mode.

### RedeliveryTriesOnListenerException

The RedeliveryTriesOnListenerException parameter specifies the number of redelivery tries when a RuntimeException is thrown on the consumer's message listener. This flag is used only when a consumer session **acknowledgment** mode is **auto\_acknowledge** or **dups\_ok\_acknowledge**. The redelivered messages will be discarded once this value is reached. This parameter is useful if the **OnMessage** logic in the consume fails occasionally due to very high usage of the threads or the CPU.

---

**Values:**

The RedeliveryTriesOnListenerException parameter default value is two. Any positive integer may be used. A negative value given to this parameter will make the client application not deliver messages to the consumer.

**Example:**

This flag is used especially when message is inserted in some other database or sent to some other server which may fail first time and subsequent calls may pass. The OnMessage logic of client should make sure that only RuntimeException is thrown.

**Dependencies:**

This flag is dependent on the consumer session **acknowledgement** mode.

## DelayInMsgDeliveryOnListenerException

The DelayInMsgDeliveryOnListnerException parameter specifies the delay in message redelivery when RuntimeException is thrown in MessageListener. This parameter is used in AUTO\_ACKNOWLEDGE or DUPS\_OK\_ACKNOWLEDGE mode only. The redelivered messages are discarded once the maximum redelivery tries value is reached.

**Values:**

The default value set for the DelayMsgDeliveryOnListenerException parameter is **-1**. This value indicates that there is no delay between redelivery tries for a message, when RuntimeException occurs in MessageListener. Any positive value in **Long range** can be assigned to this parameter. If a negative value is assigned to this parameter there will not be a delay between attempts.

**Dependencies:**

Dependencies are only applicable when the Client Session is either in AUTO\_ACKNOWLEDGEMENT or DUPS\_OK\_ACKNOWLEDGE modes.

## PublishWait

The PublishWait parameter specifies the wait interval of the publisher before the next published call. This is the minimum wait time when server crosses the PublishBackOffThreshold limit. This flag is used in scenarios where the subscriber's processing logic is going to take significant amount of time.

**Values:**

The default value for the PublishWait parameter is 50 milliseconds. (This parameter does not accept values less than or equal to zero).

---

**Example:**

This flag can be used for the pub/sub model. This flag should be increased when a larger message is accepted and more processing time for a subscriber is needed.

**Dependencies:**

The PublishWait flag can be used only if EnablePublisherSlowDown is set to yes.

Restart of server required: FALSE

## PublishWaitTimeRecheckUnits

The PublishWaitTimeRecheckUnits parameter is used for the flow control algorithm. When the PSQ size reaches 95% the publisher is made to wait repeatedly until the size drop downs to 85%. The MaxWaitTime is distributed into segments of time during which the size of the PSQ is checked. This applies to all the publishers.

**Values:**

The default value for the PublishWaitTimeRecheckUnits parameter is eight. Any positive integer may be assigned to this parameter.

**Example:**

This flag may be used when there are a certain number of slow subscribers in use.

**Dependencies:**

The PublishWaitTimeRecheckUnits parameter will be used only when **EnablePublisherSlowdown** is set to **true** and **MaxPersistentStoreSize** is not set to **-1**.

Restart of server required: FALSE

## MaxNumberOfTopics

The Maximum number of topics that can be created using this parameter by default is -1, which is allowing an infinite number of topics to be created. If this value is set to a finite value, the JMS provider will allow the creation of topics to the number stated. A message is displayed when this limit is reached.

**Values:**

The default value set for the MaxNumberOfTopics parameter is **-1**. The number of topics that can be created is **unlimited**. Any positive integer and -1 can be assigned to this parameter.

---



## EnablePublisherSlowdown

EnablePublisherSlowdown slows down the publisher when messages get stored in the disk after the session buffer overflows due to a slow subscriber and due to the PSQ size reaching its threshold value. Setting this parameter to false may lead to a message loss for slow subscribers. This property applies to all the publishers.

### Values:

The default value for the EnablePublisherSlowdown parameter is **true**. The values that can be assigned to the parameter are **true/false**.

### Example:

This flag may be used when there are slow subscribers.

### Dependencies:

Publish Slowdown behavior occurs only when MaxPersistentStoreSize is set to a finite positive integer value.

Restart of server required: FALSE

## DropOldestMessage

DropOldestMessage is a parameter indicating whether or whether new messages should be dropped after the PSQ crosses the maximum value and all Server buffers are filled.

### Values:

The default value for this parameter is **true**. The values that can be assigned to this parameter are **true/false**.

### Dependencies:

The DropOldestMessage parameter comes to use only when PublisherSlowDown is disabled in the Server and slow subscribers are active. This applies to the session level of the subscriber. This situation can also occur when the PSQ is filled with persistent messages.

Restart of server required: FALSE

## DefaultStorageTypeForTopics

The parameter DefaultTypeForTopics acquires the default storage types for Topics.

### Values:

The default value set for this parameter is **File**. The values that maybe assigned to this parameter are **File/RDBMS**. If this parameter is set to **File**, all data on topics is stored in the file based storage. If this parameter is set to **RDBMS**, all data on topics is stored in the RDBMS based storage.

---

## Dependencies

If this value is set to **RDBMS**, then the parameter **EnableRDBMS** should be set to **true**. If this value is set to **File**, then the parameter **EnableRDBMS** should be set to **false**.

## StoreMessageToDisk

Store message to disk when session buffer overflows due to slow subscriber. The messages will be stored in the PSQ only when this is set to true. If set to false, the messages will be added directly to the ConnectionBuffer which will lead to an extreme slowdown of publishers and excess message loss in some cases. This applies to all the topics.

### Values:

The default value for this parameter is **true**. The valid values that can be assigned to this parameter are **true/false**.

Restart of server required: TRUE

## EnableSnooperOnAllTopics

EnableSnooperOnAllTopics specifies whether the Snooper Service is enabled on all topics. When snooping is enabled on a queue, all the messages that are sent to this queue are copied to a topic named **SYSTEM\_MESSAGESNOOPER\_TOPIC**, so that any subscribers registered to this topic can snoop messages sent to that particular topic.

### Values:

The default value set for this parameter is **false**. The values that may be assigned to this parameter are **true/false**. When set to **true**, a SnooperListener is added to each one of the topics and all the incoming messages are snooped and added to the topic **SYSTEM\_MESSAGESNOOPER\_TOPIC**.

### Example:

This parameter can be used to monitor messages sent to the topics by the clients. In order to do this, just enable this parameter and subscribe to the topic **SYSTEM\_MESSAGESNOOPER\_TOPIC**.

Restart of server required: FALSE

## EventTopicName

Specifies the name of the topic on which events are published and processed.

### Values:

The default value for this parameter is **Events\_Topic**. This value is not assignable.

---

## IsForceFullyKillIDSubscriber

IsForceFullyKillIDSubscriber allow the forcefully killing of the Durable Subscriber. If set to true, a new Durable Subscriber gets registered with the Server. The former Durable Subscriber will be forcefully killed and this event will be successfully registered with the Server. This parameter can be applied to all Durable Subscribers.

### Values:

The default value for the IsForceFullyKillIDSubscriber parameter is **false**. The values that may be assigned to this parameter are **true/false**.

### Dependencies:

This flag is used only for Durable Subscribers. This parameter has no effect if **EnsureUniquenessOfClientID** is set to true

Restart of server required: TRUE

## MaxPersistentStoreSize

MaxPersistentStoreSize indicated the maximum size of the persistent queue in the disk. If **EnablePublisherSlowDown** is enabled, this limit will never be reached. If **EnablePublisherSlowDown** is disabled, any NP messages coming in after the limit has exceeded will be dropped. If **IgnorePSQSizeForPersistentMessages** is disabled at the same time as EnablePublisherSlowDown, even Persistent Messages will be dropped after the limit has been reached. This buffer is popularly known as PSQ and applies to each session of a slow subscriber.

### Values:

The default value for the MaxPersistentStoreSize parameter is 1073741824 bytes. The values that may be assigned to this parameter are any positive values in the **Long range** and **-1**. If set to -1, the maximum limit for the PSQ size will be unlimited.

Restart of server required: TRUE

## UseMessagePersisterForDurableSubscriber

The UseMessagePersisterForDurableSubscriber parameter is used to Enable/Disable the use of a separate algorithm used in persisting messages for a Durable Subscriber.

### Values:

The default value for the UseMessagePersisterForDurableSubscriber parameter is **false**. The values that can be assigned to this parameter are **true/false**.

Restart of server required: FALSE

---

## MaxMsgInOneRecv

MaxMsgInOneRecv parameter indicates the maximum number of messages that can be received in one call. This parameter can be applied to all subscribers.

### Values:

The default value for the MaxMsgInOneRecv parameter is **128**. The value that may be assigned to this parameter is any positive **Integer** value.

## BasicAllowedSize

BasicAllowedSize parameter indicates the maximum buffer limit on a connection. If the maximum buffer limit is exceeded, every push in the connection buffer will have to wait until some space is created. This buffer does not usually go over the maximum limit allowed since any over flow is avoided through the flow control between the session layers at the RTL and at the server.

### Values:

The default value for the BasicAllowedSize parameter is **131072** bytes. the values that can be assigned to this parameter are positive integral values.

## UseOptimizedTCPReceive

The UseOptimizedTCPReceive parameter is enabled. This algorithm was introduced in the FioranoMQ 7.5 version and is meant to provide high performance at the TCP layer on the subscriber side. This parameter may be applied to all Subscribers.

### Values:

The default value for the UseOptimizedTCPReceive parameter is **true**. The values that may be assigned to this parameter are **true/false**.

## EnableMessageMonitoring

The EnableMessageMonitoring parameter enables message monitoring and storage of data. If set to true, the data-traffic on the topic is stored in **InMemory** as well and is stored on the disk as well. Traffic can be monitored by viewing the files or by calling the required JMX API. This parameter may be applied to all Topics.

### Values:

The default value for the EnableMessageMonitoring parameter is **false**. And values that may be assigned to this parameter are **true/false**.

---

## FilePath

The FilePath parameter returns the file path set to store server messages that monitor data. Dta is stored only if **EnableMessageMonitoring** is set to **true**.

### Values:

The default value for the FilePath parameter is **%FIORANO\_HOME%\fmq\profiles\FioranoMQ\run\PUBSUB\JMSX\_MESSAGEMONITOR**. Any valid **file path** may be assigned to this parameter.

### Dependencies:

To store server message data the **EnableMessageMonitoring** flag should be set to **true**.

## TimeDuration

The TimeDuration parameter monitors the time duration in **seconds** of the flow of messages. The value of this parameter should be more than five seconds. Traffic is monitored after each interval in message flow if the **EnableMessageMonitoring** is set to **true**.

### Values:

The default value for the TimeDuration parameter is **3600** seconds. The values that may be assigned to this parameter are any positive integer values greater than 5.

## PurgeLevelIndex

The PurgeLevelIndex parameter indicated the number of persistent messages allowed prior after which purging is done. This parameter will function when **OptimizedTCPReceive** is set to **false**. This parameter may be applied to all Topics.

### Values:

The default value for the PurgeLevelIndex parameter is **100**. The values that may be assigned to this parameter are any positive integer values.

### Dependencies:

This parameter is used only for **persistent** messages and only when **UseOptimizedTCPReceive** is set to **false**.

Restart of server required: TRUE

## MinPurgeDifference

The MinPurgeDifference parameter indicates the minimum number of persistent messages allowed after which purging is done. Purging is done in batches in the Server and this parameter indicates the minimum number of **delete requests** that the server will accumulate prior to deleting messages. This parameter may be applied to all Topics.

---

**Values:**

The default value for the MinPurgeDifference parameter is **50**. The values that may be assigned to this parameter are any positive integer values.

**Dependencies:**

This parameter is used only for **persistent** messages and only when **UseOptimizedTCPReceive** is set to **false**.

Restart of server required: TRUE

## AllowDeletionOfSubtopics

AllowDeletionOfSubtopics is a boolean parameter determining if deletion of SubTopics is allowed. If set to true then deleting a topic will automatically delete the SubTopics. This parameter may be applied to all Topics.

**Values:**

The default value for the AllowDeletionOfSubtopics parameter is **true**. The values that may be assigned to this parameter are **true/false**.

Restart of server required: FALSE

## MessagePublishTimeout

The MessagePublishTimeout parameter indicates the maximum time a publisher will wait while trying to push messages to a connection level buffer when it is full. This parameter also indicates the maximum time a publisher will wait to push the message to the PSQ after it has reached 95% of its maximum limit. This parameter applies to non\_persistent messages as well as for persistent messages. The waiting time does not end until the buffer reaches 85% usage. This parameter may be applied to all the publishers.

Setting the MessagePublishTimeout to a -1 ensures that the publisher does not slow down.

**Values:**

The default value for the MessagePublishTimeout parameter is 120000 milliseconds. The values that can be assigned to this parameter are -1 (no wait) or any positive integer value.

Restart of server required: FALSE

## PublishBackoffThreshold

The PublishBackoffThreshold parameter indicates the PSQ size threshold after which the backoff algorithm is activated. Once the threshold is reached then flow control will be activated and the publishers will be made to wait for the buffers to clear.

---

**Values:**

The default value for the PublishBackoffThreshold parameter is **0.6**. The values that may be assignable to this parameter are any positive Double values < 1.

Restart of server required: FALSE

## IgnorePSQSizeForPersistentMessages

The IgnorePSQSizeForPersistentMessages parameter indicates whether to persist persistent messages in PSQ even through the PSQ is full. If set to **true** if the **MaxPersistentStoreSize** (PSQ) is exceeded the messages will be stored to the disk. This parameter may be applied to all Publishers.

**Values:**

The default value for the IgnorePSQSizeForPersistentMessages parameter is **true**. The values that may be assignable to this parameter are **true/false**.

**Dependencies:**

This parameter is applicable only for messages with in the **persistent** delivery mode.

Restart of server required: FALSE

## EnableSessionStateChangeNotification

This parameter defines whether to raise notifications related to the topicSession's state changes corresponding to slow subscribers. That is, whenever the underlying subscriber undergoes state changes - becomes slow or normal - a notification is raised to all event listeners.

In order to receive this event, the the object (which implements javax.jms.NotificationListener) should be added on the MBean specified by the object name -

"Fiorano.jmx.notifications:ServiceType=EventManager,Name=TopicConnectionEventManager".

Kindly refer to the "fmq/samples/JMX/JMXNotifications.java" for more information.

**Values:** The default value for this parameter is FALSE and the valid values are TRUE and FALSE.

## LoadLVIndicesAtLookup

This parameter determines whether to load the Last value cache indices at the time when the message is first sent to the JMS Topic. If set to true, the Last value cache indices are loaded at the time of Topic lookup. These indices are used to identify the JMS Message that is stored in the LV-Cache for a particular LV-Cache Key.

---

## Values

This parameter accepts boolean values - 'true' or 'false'. Default value is 'false', which means that the LV-Cache indices are loaded into the Server's memory when the first JMS Message arrives on the Topic.

## Example

This parameter may be used to potentially decrease the time taken for the first 'Publish' call. In case the LV-Cache has thousands of messages, it takes several milliseconds to load this data into the Server's memory.

## Dependencies

This parameter is only used if EnableLastValueCache on the JMS Topic is set to 'true'.

## IgnoreNullLVCKey

This parameter determines whether to ignore the message sent to a JMS Topic on which LV-Caching is enabled with cache-key property not set. If set to false, an exception is thrown if the message has no cache-key set.

## Values

This parameter accepts boolean values - 'true' or 'false'. Default value is 'true', which means that when the JMS Message arrives on the Topic with no LV-Cache key set, it is ignored.

## Example

This flag may be used to potentially stop publishing messages from a normal Publisher which doesn't send messages supposed to the Topic on which Last Value Cache is enabled.

## Dependencies

This parameter is only used if EnableLastValueCache on the JMS Topic is set to 'true'.

## FlushLVCDDataAtStartup

This parameter determines whether to clean-up LVC data stores at the time of start-up of the FioranoMQ Server.

## Values

This parameter accepts boolean values - 'true' or 'false'. Default value is 'false', which means that when the messages stored in the LV-Cache are not deleted and any new Subscribers will get those messages.

## Example

This flag may be used to potentially start the Last Value Caching afresh and to flush the data stored in the Topics' LV-Cache after the Server's each run.

---



**Dependencies**

This parameter is only used if EnableLastValueCache on the JMS Topic is set to 'true'.

# Chapter 6: Topic Level Configurations

---

This chapter explains the parameters that can be configured for JMS storage objects of type 'Topic'. In general, these parameters are the most common ones used in the Publish-Subscribe (PubSub) model of JMS and they can be configured in the default profile at the node FioranoMQ->Fiorano->mq->ptp->Topics->specific topickis through Offline configuration using Studio.

For information on how to configure the FioranoMQ Server in Offline mode, refer to **Chapter 3 Offline Configuration Through Profile Manager** and for Online Configuration (through the Web Management Console), refer to **Chapter 30 FioranoMQ Web Management Console** of *FioranoMQ Handbook*.

**Note:** From FioranoMQ 9.1.0 release onwards, a unique Destination Level Configuration support is included. For more on this, please refer to section **29.1 Support for Destination Level Configuration** in the *FioranoMQ Handbook*

## CacheKeyPropertyName

CacheKeyPropertyName parameter determines the property name used to define the LV-Cache Key, in the JMS Message, using which the message is stored in the Topic's LV-Cache.

### Values:

The default value for this parameter is **LVCacheKey**.

Restart of server required: TRUE

## CachePropertyName

CachePropertyName parameter determines the property name used to define whether the JMS Message should be considered to be stored in the Topic's LV-Cache.

### Values:

The default value for this parameter is **IsLVCache**.

Restart of server required: TRUE

## EnableLastValueCache

EnableLastValueConfig parameter determines whether to enable LV-Caching on the corresponding JMS Topic.

---

**Values:**

The default value for this parameter is **false**. Valid values for this parameter are **true/false**

Restart of server required: TRUE

## EnableJournaling

EnableJournaling specifies whether Journaling Service is enabled on this Topic. By default, on Snooper Topics such as SYSTEM\_MESSAGESNOOPER\_TOPIC and SYSTEM\_MESSAGESNOOPER\_QUEUE and Events topic EVENTS\_TOPIC, Journaling is disabled.

**Values:**

The default value for this parameter is **false**. Valid values for this parameter are **true/false**.

Restart of server required: FALSE

## MaxPublisherBlockTime

MaxPublisherBlockTime is the maximum time in milliseconds for which a Publisher will wait while trying to push the messages to the PSQ after it has reached 95% of its max limit. This applies to all the publishers.

**Values:**

The default value for this parameter is **120000**. Any positive integer can be assigned as a value for this parameter.

Restart of server required: FALSE

## ParConsumptionLVCache

ParConsumptionLVCache parameter determines whether to enable parallel consumption of LV-Cache messages from Subscriber's copy. If set to false, the consumption of messages will start only after the Subscriber completely copies the Topic's LV-Cache copy.

**Values:**

The default value for this parameter is **false**. Valid values for this parameter are **true/false**.

Restart of server required: TRUE

Remaining Topic parameters are mentioned in Chapter5: Topic Subsystem Level Configurations

# Chapter 7: Connection Manager Configurations

---

This chapter explains the parameters that can be configured for the connection manager used in the FioranoMQ Server. In general, these parameters are the most common ones used for connection management in the server and they can be configured in the default profile at the node FioranoMQ->Fiorano->socketAcceptors->port-1->ConnectionManager through Offline configuration using Studio.

For information on how to configure the FioranoMQ Server in Offline mode, refer to **Chapter 3 Offline Configuration Through Profile Manager** and for Online Configuration (through the Web Management Console), refer to **Chapter 30 FioranoMQ Web Management Console** and on Connection Management, refer to **Chapter 4 Connection Management** of *FioranoMQ Handbook*.

## Default

Default identifies whether the Connection Manager is set as a default option. All connection factories contain URL information of the Connection Manager. If no Connection Manager has its flag set to **true** the connection factories will retrieve their URL information from the default server URL.

### Values:

The default value for the Default parameter is **true**. The values assignable to this parameter are **true/false**.

## CFNameAppender (Not being used in FioranoMQ)

The CFNameAppender parameter specifies the suffix to be attached to the ConnectionFactory created for the ConnectionManager.

### Values:

The default value for the CFNameAppenderparameter is null. The values assignable to this parameter may consist of a string of characters.

## ReaderCacheDisabled

ReaderCacheDisabled is a boolean parameter indicating whether the connection cache is created on the read socket. This cache is used while reading bytes from Sockets. If this parameter is set to **true**, then the appropriate amount of memory is allocated for each Socket Read. If set to **false** memory is allocated for Socket Read based on the exact memory needed decreasing the number of memory re-allocations.

---

**Values:**

The default value for the ReaderCacheDisabled parameter is **false**. The values that can be assigned to this parameter are **true/false**.

## TCPWindowSize (Not being Used in FioranoMQ)

TCPWindowSize is used for the three ways handshaking process required for connection creation.

**Values:**

The default value for the TCPWindowSize parameter is **133120** bytes. The values assignable to this parameter are any positive values in Long **Range**.

## HandshakeInWorkerThread

The HandshakeInWorkerThread is a boolean parameter indicating whether the HandShaking process was performed while accepting the connection request from the client or when creating the socket initialization context.

**Values:**

The default value for the HandshakeInWorkerThread parameter is **true**. The values that may be assigned to this parameter are **true/false**.

## MagicTimeout

The MagicTimeout parameter sets the socket timeout for the socket that is created. If a request does not arrive on the socket within the interval specified, a socket cleanup is performed.

**Values:**

The default value for the MagicTimeout parameter is **60000** seconds. The values that may be assignable to this parameter are any non-negative integer values. If this value is set to zero the 'timeout' is considered to be infinite.

**Example:**

If the MagicTimeout value is set to 60000 and a connection is made to the FioranoMQ Server and the Server fails to communicate, the socket will be cleared after one minute. This connection must communicate with the JMS Server within one minute or the Socket will be cleared and the connection closed.

## Port

The Port parameter is used for binding the socket at the time of Server startup.

---

**Values:**

The default value set for the MagicTimeout parameter is **1856**. A valid port value is between 0 and 65535.

**Example:**

if the MagicTimeout value is set to **1856**, which is the default value, and the machine IP address is **192.168.1.209**, clients have to mention **http://192.168.1.209:1856** as the provider URL to connect to the JMS provider.

## Protocol

The Protocol parameter is used for establishing a connection between the Client and the Server.

**Values:**

The default value set for the Protocol parameter is **TCP**. The values that may be assignable to this parameter are TCP/HTTP/SUN\_SSL/HTTPS\_SUN.

- TCP - Accepts connections based on the TCP Protocol.
- HTTP - Accepts Connections based on the HTTP Protocol.
- SUN\_SSL - Accepts Secured Connections based on the TCP Protocol.
- HTTPS\_SUN - Accepts Secured Connections based on the HTTP Protocol.

**Dependencies:**

If the Protocol is set to either SUN\_SSL or HTTPS\_SUN, **SSLEnabled** must be set to **true**.

## UseNagle

Use Nagle is a boolean parameter indicating whether the Nagle Algorithm was used in creating the socket. Using the Nagle Algorithm enables improving the efficiency of the TCP/IP networks by reducing the number of packets that need to be sent over the network. The Nagle Algorithm is used to automatically concatenate a number of small buffer messages. The process of concatenating several small messages (called nagling) increases the efficiency of a network application system by decreasing the number of packets to be sent.

**Values:**

The default value set for the UseNagle parameter is **false**. The values that can be assigned to the UseNagle parameter are **true/false**.

## MonitoringRequest

The MonitoringRequest parameter is the default monitoring request ID sent as a validation for communication.

---

**Values:**

The default value for the MonitoringRequest parameter is **13**.

## MonitoringResponse

The Monitoring Response parameter is the default monitoring request response sent as a validation for communication.

**Values:**

The default value for the Monitoring Response parameter is null.

## EnforceJsseAuthentication

The EnforceJsseAuthemtication parameter checks whether authentication is to be done for JSSE client requests accept by the S. The value of this parameter is preset and useful for sockets in the server.

**Values:**

The default value for the EnforceJsseAuthemtication parameter is **false**. The values considered valid by this parameter are **true/false**.

- True - If client authentication is required on newly accepted connections.
- False - If client authentication is not required on newly accepted connections.

**Example:**

If this parameter is set to true and the client does not provide authentication information, the server socket will not continue communication with the client and the connection will be dropped.

## MaxClientConnectionsCount

The MaxCientConnectionsCOunt is the maximum number of client connections allowed with the Connection Manager. A value of -1 indicates no upper limit for connections allowed.

**Values:**

The default value for this parameter is **1024**. The values that this parameter considers valid are -1 and any positive integer value. If this value is set to -1, there is no maximum client connection limit..

**Example:**

If the value for this parameter is set for 200 and 200 external connections from clients are made to the server, any attempts to create more connections which are not LPC Enabled will not be successful and all connections will be dropped.

---

## AdminConnection (Not being used)

AdminConnection serves the client by checking whether the connection is an Administrative Connection or a Normal Connection.

### Values:

The default value set for the AdminConnection parameter is **false**. The values considered valid by this parameter are **true/false**.

## Path

Deprecated attribute. Please refer to SSL documentation. Root directory in which this connection manager searches for digital signatures for handling secure connections

### Values:

The default value for the Path parameter is certs. Any valid file may be assigned to this parameter.

### Example:

By default, the Path parameter in the FioranoMQ profile directs queries regarding digital signatures to the folder *\$FIORANO\_HOME/fmq/profiles/FioranoMQ/certs*.

## ServerAddress

ServerAddress is the InetAddress of the local machine that the FioranoMQ Server needs to bind with. This option is useful when the FioranoMQ Server is running on multi-homed machines.

### Values:

The default value for the Server Address parameter is null. A valid machine name or a textual representation of the a machine's IP address may be assigned as a value for this parameter.

### Example:

If a machine has an IP address of <192.168.1.209> and hostname of <example.hostname>, either one of these may be given as its ServerAddress.

## HandShakingDisabled

HandShakingDisabled is a boolean parameter indicating whether the **handshake** is disabled is enabled upon connection creation.

### Values:

The default value for the HandShakingParameter parameter is **false**. The values that that are considered valid for this parameter are **true/false**.

---



- True – Set to True if a **handshake** between the client and the server is not needed after creating a new connection.
- False – Set to False to perform a **hand shake** between the client and the server after creating a new connection.

**Dependencies:**

Refer to the special note below.

**Special Note:**

When setting the value of the HandShakingDisabled parameter to true in the server set a System Property **DisableHandShake=true** in the client JVM when.

**Caution:** Setting this parameter may make the Server DOS attack prone making the client JVM hang if it is unable to set the Client System Property for the same.

## ManagerClassName

Deprecated Attribute. Please refer to SSL documentation. Class Name of the Security Manager for wrapping TCP/HTTP communication. This is an implementation of IExSecurityManager. One can write and plug-in his server security manager. Possible default values are fiorano.jms.ex.sm.def.DefaultJSSESecurityManager

**Values:**

The default value considered valid for the ManageClassName parameter is fiorano.jms.ex.sm.def.DefaultJSSESecurityManager. The value that is considered valid for this parameter.

**Example:**

The ManageClassName is an implementation of IExSecurityManager. The parameter may be used to manage certificates which are used for handling secure connections.

**Dependencies:**

The ManageClassName parameter is used only when SSLEnabled is set to true.

## FioranoMQServer

The FioranoMQServer is a boolean value that determines whether the connection created is for the FioranoMQ Server or if it is for external servers.

**Values:**

The default value for the FioranoMQServer parameter is **true**. The values considered valid for this parameter is **true/false**.

- True - Connection created is for the FioranoMQ Server.
  - False – Connection created if for FES/FPS Servers.
-

## UseForPeerToPeerCommunication (Not being used in FioranoMQ)

UseForPeerToPeerCommunication is a boolean parameter which determines whether the connectionManager created should be used to communicate with Peer Servers. (This parameter is applicable to FPS only.)

### Values:

The default value for the UseForPeerToPeerCommunications parameter is **false**. The values considered valid for this parameter is **true/false**.

## UseSystemPropsForSSL

Boolean which determines whether System properties like javax.net.ssl.keyStore to load key store and trust store for SSL Communication. If we enable this parameter, then the FioranoMQ Server assumes that the "Context", in which the SSL Server Socket is created, is initialized by the JDK using the system properties like -

- javax.net.ssl.keyStore
- javax.net.ssl.keyStorepassword
- javax.net.ssl.keyStoreType
- javax.net.ssl.trustStore
- javax.net.ssl.trustStorePassword
- javax.net.ssl.trustStoreType
- javax.net.debug

Please see SSL documentation for further information.

### Valid Values:

True/False. Default value for this parameter is false.

## CipherSuiteList

Semi-colon separated list of Cipher Suites to be enabled for SSL/TLS Communication. By default every cipher suite supported by JDK/JRE is enabled.

### Valid Values:

Any cipher suite supported by the JDK/JRE. This list can be obtained by invoking "javax.net.ssl.SSLServerSocket.getSupportedCipherSuites()" API. Default value for this parameter is null, which means that every cipher suite supported is enabled.

---

# Chapter 8: Dash Board Configurations

---

This chapter explains the parameters that can be configured for the Dashboard, used as the Monitoring and Administration tool for the FioranoMQ Server. These parameters can be configured in the default profile at the node FioranoMQ->Fiorano->etc->JettyServer through Offline configuration using Studio.

For information on how to configure the FioranoMQ Server in Offline mode, refer to **Chapter 3 Offline Configuration Through Profile Manager** and for information on the Web Management Console, refer to **Chapter 30 FioranoMQ Web Management Console** of *FioranoMQ Handbook*.

## JettyServer

The parameters present in **Fiorano->etc->JettyServer** are explained in this chapter.

## MaxThreads

MaxThreads are the maximum number of threads that can be created for the Jetty Server that is running.

The MaxThreads parameter allows the User to configure the maximum number of threads the dashboard may have active at any time. This value can be decreased if the User does not expect that much traffic will be directed towards the Jetty Server.

### Default Value:

The Jetty Server thread pool has a default limit of 250 threads.

## EnableStart

EnableStart is a boolean value describing whether the Jetty Server should be activated along with FioranoMQ Server.

If the User does not wish the Jetty Server to be setting the Jetty Server to false will prevent the Server from running.

### Valid Values:

- Yes (in Studio)/True - The Jetty Server is started along with the FioranoMQ Server.
- No (in Studio)/False - The Jetty Server is not started along with the FioranoMQ Server.

### Default Value:

Yes (In Studio)/True - The Jetty Server is started along with the FioranoMQ Server.

---

## MinThreads

The MinThreads parameter is the minimum number of threads that are created in the dashboard that is running.

The MinThreads parameter allows the User to configure the minimum number of threads that should be present in the dashboard thread pool. This value can be increased if the user expects high traffic directed towards the dashboard.

### Default Value:

There should be a minimum of 10 threads by default in the Jetty Server thread pool.

## LowThreads

The LowThreads parameter allows the User to set the low threads threshold for the thread pool of the Jetty Server. A low resource state detects a threshold or a limit set on the number of threads that the Jetty Serverthread pool may have. The limit set on the number of threads is specified by this parameter.

### Default Value:

When a low resource is detected, the Jetty Serverthread pool threshold, by default, is set to 25.

## MaxIdleTime

The MaxIdleTime parameter sets the maximum idle time for a connection. The maximum idle time is applied while:

- Waiting for a new request to be received on a connection.
- Reading the headers and content of a request.
- Writing the headers and content of a response.

### Default Value:

The maximum time, by default, that the Jetty Server may remain idle is 30000 milliseconds.

### Dependencies:

LowResourceMaxIdleTime

## LowResourceMaxIdleTime

The LowResourceMaxIdleTime is the value specified to reduce the maximum idling time of a connection when a 'low resource' status is detected.

---

**Default Value:**

The default value of the MaxIdleTime when there is a low resource state is 5000.

**Dependencies:**

MaxIdleTime

**PortNumber**

PortNumber is the value that allows the User to configure the Jetty Server to run on different ports. When the User wants to start two or more instances of the FioranoMQ server on the same box, the jetty server port for each of these Server instances must be different as all of them cannot be bound to the same port.

**Default Value:** The default port for the jetty server is 1790.

# Chapter 9: Security Configuration

---

This chapter explains the configurable parameters related to the FioranoMQ Security module (Principal and ACL Managers) in the server. These parameters can be configured in the default profile at the node FioranoMQ->Fiorano->security->AclManager->\* and FioranoMQ->Fiorano->security->PrincipalManager->\* through Offline configuration using Studio.

For information on how to configure the FioranoMQ Server in Offline mode, refer to **Chapter 3 Offline Configuration Through Profile Manager** and for information on FioranoMQ Security, refer to **Chapter 7 FioranoMQ Security** of *FioranoMQ Handbook*.

## SecuritySubSystem

Presented below are the details of the parameters in FioranoMQ->Fiorano->Security->SecuritySubSystem

### UseAuthenticationModules

Specifies whether to use externally plugged authentication modules when authenticating a user.

**Default value:** false

**Valid values:** true, false

### ConfigurationName

Specifies the JAAS configuration name for loading externally plugged authentication modules to be used for authenticating a user. As a login configuration file may contain many configurations that can be used by different applications, this parameter is used for loading the specific configuration to be used by this FioranoMQ server.

**Default value:** SampleAuthenticator

**Valid values:** A valid configuration name present in the configuration file.

### ConfigurationFileName

Specifies the JAAS configuration file name which has the necessary information about the LoginModule(s) for loading externally plugged authentication modules to be used for authenticating a user. This file should follow the syntax and semantics of JAAS Login Configuration File.

**Default value:** ../Utilities/ExternalAuthnModule/src/sample\_authn.config

**Valid values:** Any valid file location

---

## NativeFileBasedAclManager

Presented below are the details of the parameters in **FioranoMQ->Fiorano->Security->AclManager->NativeFileBasedAclManager**.

### MaxAcePerAcl

The MaxAcePerAcl parameter provides the ability to limit the maximum number of access control entries for each ACL.

#### Valid value:

Any string

The default value of this parameter is integer greater than 0.

## LdapBasedAclManager

Following are the parameters present in FioranoMQ->Fiorano->Security->AclManager ->LdapBasedAclManager.

### LdapProviderUrl

This parameter denotes the LDAP Server's URL. For correct URL format, please refer to your LDAP Server's documentation. This value along with LdapProviderDn, later on while initializing the LDAP context, is passed in the environment with key as 'java.naming.provider.url'.

Valid value: The value of the property should contain a URL string (e.g. "ldap://somehost:389").

Default value is ldap://164.164.128.11:389/

### LdapProviderDn

This parameter points to the base domain on LDAP Server, under which FMQ would create its repository. This value along with LdapProviderUrl, later on while initializing the LDAP context, is passed in the environment with key as 'java.naming.provider.url'.

Valid value: The value should be a distinguished name of an LDAP entry which uniquely identifies the entry.

Default value is "o=fiorano,c=us".

---

## Principal

This parameter takes input the LDAP User Name. This is the user name which would be used to connect to the LDAP Server. This is provided as "java.naming.security.principal" (caller authentication to LDAP service is done using this) when creating the javax.naming.directory.InitialDirContext to the LDAP provider for performing operations on it. This is LDAP-provider specific.

Valid value: This parameter takes any valid user name in String representation.

Default value is "cn=FMQRoot,o=fiorano,c=US".

## Credentials

This parameter takes input the LDAP Server Login Password. This is provided as "java.naming.security.credentials" (caller authentication to LDAP service is done using this) when creating the javax.naming.directory.InitialDirContext to the LDAP provider for performing operations on it.

Valid value: This parameter takes any valid password in String representation.

Default value is "secret".

## LdapInitialCtxFactory

This parameter takes input the class name for LDAP Server's Initial Context Factory to be supplied to Initial Context. This is provided as "java.naming.factory.initial" when creating the javax.naming.directory.InitialDirContext to the LDAP provider for performing operations on it.

Valid value: The value of the property should be the fully qualified class name of the factory class that will create an initial context.

Default value is "com.sun.jndi.ldap.LdapCtxFactory".

## LdapAclContextDn

This parameter points to the location at which ACLs would be stored. This parameter takes a String value which denotes the name of the tree-node under which different ACLs are to be created.

Valid value: The value should be a relative distinguished name of an LDAP entry under the main entry (provided in LdapProviderDn) which uniquely identifies the entry.

Default value is "cn=ACL".

---



### **LdapSecurityAuthentication**

The parameter value provided with LdapSecurityAuthentication is supplied as "java.naming.security.authentication" in the environment while creating the InitialDirContext to the LDAP provider. Possible values are none, simple, strong. "none" for no authentication, "simple" for clear-text username-password authentication and "strong" for user-binding using strong authentication mechanisms via SASL.

Valid value: This parameter takes input "none" or "simple" or "strong".

Default value is "simple".

### **LdapPollInterval**

This parameter denotes the interval (in milliseconds) after which the LDAP Server Connection is polled. Negative Value disables polling.

Valid value: This parameter takes input any integral value.

Default value is "-1".

### **LdapPrimaryServerReconnectAttempts**

This parameter denotes the number of reconnect attempts LDAP primary server makes in case the LDAP server connection polling is unsuccessful.

Valid value: This parameter takes input any integral value.

Default value is "5".

### **BackupLdapProviderUrl**

This parameter denotes the backup LDAP server provider URL, which is tried when the primary LDAP Server becomes unavailable. See LdapProviderUrl.

Valid value: See LdapProviderUrl.

Default value is "".

### **BackupLdapProviderDn**

This parameter points to the base domain on Backup LDAP Server, under which FMQ would create its repository. See LdapProviderDn.

Valid value: See LdapProviderDn.

Default value is "".

---

### **BackupPrincipal**

This parameter denotes the backup LDAP Server's user name. This is the user name which would be used to connect to the Backup LDAP Server. See Principal.

Valid value: See Principal.

Default value is "cn=FMQRoot,o=fiorano,c=US".

### **BackupCredentials**

This parameter denotes the backup LDAP Server's login password. See Credentials.

Valid value: See Credentials.

Default value is "secret".

### **BackupLdapInitialCtxFactory**

This parameter denotes the class name for LDAP Server's Initial Context Factory to be supplied to Initial Context. See LdapInitialCtxFactory.

Valid value: See LdapInitialCtxFactory.

Default value is "".

### **BackupLdapSecurityAuthentication**

This parameter denotes the backup LDAP server's security authentication protocol. See LdapSecurityAuthentication.

Valid value: See LdapSecurityAuthentication.

Default value is "none".

### **AclEntryObjectClasses**

Comma separated object class names for an ACL entry in the LDAP provider. For storing ACL's in an LDAP provider, the LDAP-provider should be made configurable to store the java objects as per RFC 2713 Schema for representing Java objects in LDAP.

Valid value: Comma-separated strings which denote object class names of an LDAP-provider.

Default value is "top,javaContainer,javaObject".

---

## XMLFileBasedAclManager

Following are the parameters present in Fiorano->security->AclManager->XMLFileBasedAclManager

### Path

String value of path where the XML file containing the persisted ACLs is created

Default Value: realm/acl

### Filename

Name of the file in String format that stores the persisted ACL information

**Default Value:** acl.xml - The default xml filename

### MaxAcePerAcl

Number of Maximum Access control entries per ACL in integer format

**Valid values:** Integer greater than zero

Default value: 100

## RdbmsBasedAclManager

Following are the parameters present in Fiorano->security->AclManager->RdbmsBasedAclManager

### MaxAcePerAcl

Number of Maximum Access control entries per ACL in integer format

**Valid value :** Integer greater than zero

Default value: 100

### Url

URL for RDBMS Server in String format

**Example:** jdbc:oracle:thin:@localhost:1521:ORCL for oracle server

---

## Password

String value of password for RDBMS User - Used for connecting to the RDBMS Server

## Username

String value of database User Name - Used for connecting to the RDBMS Server.

Default Value: sa

## DBDriver

JdbcDriver used for RDBMS based data storage in String format

**Default Value:** org.hsqldb.jdbcDriver - The default database driver class name

## ConnectionTimeoutInterval

Integer value of database connection open timeout

**Default Value:** 10000 - The time in milliseconds for connection timeout

**Valid Value:** Non negative Integer with value zero representing wait forever

## ReconnectTimeInterval

Integer value of time interval (in msec) between two reconnect attempts in disconnected state.

**Default Value:** 10000 - The time in milliseconds taken by Acl Manager between reconnect attempts

**Valid Value:** Non negative Integer

## EnableReconnect

Boolean value that specifies if Acl Manager has to try to reconnect to database server in case of a connection breakup

Valid Values:

- **True** - Enables reconnect attempts to database server when the connection is down.
- **False** - Disables reconnect attempts to database server when the connection is down.

**Default Value:** True - Enables reconnect attempts to database server when the connection is down.

---

## StatementFile

String that represents name of the properties file that is used to define name-value properties specific to a particular database.

**Default Value:** aclsqstatements.properties - The default properties used which is located at %FIORANO\_HOME%/fmq/profiles/%YOUR\_PROFILE%/conf

## ConnectionLostErrorMessage

String representing error message to be posted in case of lost connection

Allows the user to set the custom messages to be displayed when connection to the RDBMS server is lost

**Default Value:** DB\_CONNECTION\_LOST - The default connection lost message.

## InitializeDB

Boolean value to enable/disable initialization of the underlying Database by creating necessary tables on startup if required

Valid values:

- **True**- Enables initializing the DB
- **False** - Disables initializing the DB

Default Value: True - Enables initializing the DB.

## FileDBManager3

Presented below are the details of all the parameters in **FioranoMQ->Fiorano->Security->AclManager->FileDBManager->FileDBManager3**.

## Path

The security configuration, the ACL, is stored in the file based data storage in the path specified by the Path parameter.

**Valid values:**

The default values are **SDB/REALM.ACL**

The path specified is relative to the run directory of each FioranoMQ profile.

---

## DeletedThresholdPercent

A cache stores and manages the list of all the tables pertaining to group based information in the file-storage based ACL. After repeated modification of the ACL, old entries in the table are marked as deleted. This value provides a threshold percentage of deleted entries after which the Cache Compaction Process is started. At the end of the Cache Compaction Process the table will not have any deleted entries. Since cache compaction involves CPU intensive File Operations, this flag is to be used along with **DeletedThresholdCount** to ensure it is not invoked too often.

### Valid values:

The default value of this parameter is **50**. This indicates that if the ratio of deleted entries to total entries is equal to or greater than 0.5 then the Cache Compaction Process will be invoked.

The range of integer values in java that are considered valid by the DeletedThresholdPercent parameter are  $-2^{32}$  to  $2^{32} - 1$ .

All values less than or equal to zero provide the same result. All values greater than or equal to 100 provide the same result.

### Example:

Use the example of the ratio of deleted entries/total entries in the table. If there a chance that many entries will be marked deleted often, a higher number should be entered as the parameter value.

## DeletedThresholdCount

A cache stores and manages the list of all tables pertaining to group based information in the file-storage based ACL. After repeated modification of the ACL, old entries in the table are marked as deleted. This value provides a threshold count of deleted Entries for starting the Cache Compaction Process. At the end of the Cache CompactionProcess the table will not have any deleted entries. Since cache compaction involves CPU intensive File Operations, this flag is to be used along with DeletedThresholdPercent to ensure it is not invoked too often.

### Valid values:

The default value of this parameter is **10**.

The range of integer values in java that are considered valid by the DeletedThresholdCount parameter are  $-2^{32}$  to  $2^{32} - 1$ .

All values less than or equal to zero provide the same result.

### Example:

Although the DeleteThresholdPercent provides a ratio based method of ensuring that the Cache Compaction Process does not occur too often, it does not provide an absolute lower limit of the number of deleted entries needed to trigger a Cache Compaction. It is best to choose a value that is high so as to enable triggering a Cache Compaction.

---

## DbTableNamePrefix

The database table names are usually prefixed with a string that can be modified by the DbTableNamePrefix parameter.

### Valid value:

The default value of the DbTableNamePrefix is #

Any String value is a valid parameter.

### Example:

If the database table is to be saved in its current state and the the current state is to be saved to be used in the future, modify the prefix to another relevant string and change it back to the original string when the saved state of the database table is to be used.

## NativeFilePrincipalManager

Presented below are the details of the parameters in **FioranoMQ->Fiorano->Security->PrincipalManager->NativeFilePrincipalManager**.

### MaxPasswordLength

Each principal is allotted a password and the MaxPasswordLength parameter enables the configuration of the maximum allowable password length.

### Valid value:

The default value of the MaxWordLength is **50**.

The range of integer values in java that are considered valid by the MaxPasswordLength parameter are  $-2^{32}$  to  $2^{32} - 1$ .

All values less than or equal to zero provide the same result.

### MaxMemberCount

The MaxMemberCount parameter defines the maximum number of members a group may have.

### Valid value:

The default value of this parameter is **50**.

The range of integer values in java that are considered valid by the MaxMemberCount parameter are  $-2^{32}$  to  $2^{32} - 1$ .

All values less than or equal to zero provide the same result.

---

## LdapPrincipalManager

Following are the parameters present under the FioranoMQ->Fiorano->Security->PrincipalManager->LdapPrincipalManager.

### LdapProviderUrl

This parameter denotes the LDAP Server's URL. For correct URL format, please refer to your LDAP Server's documentation. This value along with LdapProviderDn, later on while initializing the LDAP context, is passed in the environment with key as 'java.naming.provider.url'.

Valid value: The value of the property should contain a URL string (e.g. "ldap://somehost:389").

Default value is ldap://164.164.128.11:389/

### LdapProviderDn

This parameter points to the base domain on LDAP Server, under which FMQ would create its repository of users and groups. This value along with LdapProviderUrl, later on while initializing the LDAP context, is passed in the environment with key as 'java.naming.provider.url'.

Valid value: The value should be a distinguished name of an LDAP entry which uniquely identifies the entry.

Default value is "o=fiorano,c=us".

### Principal

This parameter takes input the LDAP User Name. This is the user name which would be used to connect to the LDAP Server. This is provided as "java.naming.security.principal" (caller authentication to LDAP service is done using this) when creating the javax.naming.directory.InitialDirContext to the LDAP provider for performing operations on it. This is LDAP-provider specific.

Valid value: This parameter takes any valid user name in String representation.

Default value is "cn=FMQRoot,o=fiorano,c=US".

### Credentials

This parameter takes input the LDAP Server Login Password. This is provided as "java.naming.security.credentials" (caller authentication to LDAP service is done using this) when creating the javax.naming.directory.InitialDirContext to the LDAP provider for performing operations on it.

Valid value: This parameter takes any valid password in String representation.

---



Default value is "secret".

### **LdapInitialCtxFactory**

This parameter takes input the class name for LDAP Server's Initial Context Factory to be supplied to Initial Context. This is provided as "java.naming.factory.initial" when creating the javax.naming.directory.InitialDirContext to the LDAP provider for performing operations on it.

Valid value: The value of the property should be the fully qualified class name of the factory class that will create an initial context.

Default value is "com.sun.jndi.ldap.LdapCtxFactory".

### **LdapSecurityAuthentication**

The parameter value provided with LdapSecurityAuthentication is supplied as "java.naming.security.authentication" in the environment while creating the InitialDirContext to the LDAP provider. Possible values are none, simple, strong. "none" for no authentication, "simple" for clear-text username-password authentication and "strong" for user-binding using strong authentication mechanisms via SASL.

Valid value: This parameter takes input "none" or "simple" or "strong".

Default value is "simple".

### **LdapPollInterval**

This parameter denotes the interval (in milliseconds) after which the LDAP Server Connection is polled. Negative Value disables polling.

Valid value: This parameter takes input any integral value.

Default value is "-1".

### **LdapPrimaryServerReconnectAttempts**

This parameter denotes the number of reconnect attempts LDAP primary server makes in case the LDAP server connection polling is unsuccessful.

Valid value: This parameter takes input any integral value.

Default value is "5".

### **BackupLdapProviderUrl**

This parameter denotes the backup LDAP server provider URL, which is tried when the primary LDAP Server becomes unavailable. See LdapProviderUrl.

Valid value: See LdapProviderUrl.

---

Default value is "".

### **BackupLdapProviderDn**

This parameter points to the base domain on Backup LDAP Server, under which FMQ would create its repository. See LdapProviderDn.

Valid value: See LdapProviderDn.

Default value is "".

### **BackupPrincipal**

This parameter denotes the backup LDAP Server's user name. This is the user name which would be used to connect to the Backup LDAP Server. See Principal.

Valid value: See Principal.

Default value is "cn=FMQRoot,o=fiorano,c=US".

### **BackupCredentials**

This parameter denotes the backup LDAP Server's login password. See Credentials.

Valid value: See Credentials.

Default value is "secret".

### **BackupLdapInitialCtxFactory**

This parameter denotes the class name for LDAP Server's Initial Context Factory to be supplied to Initial Context. See LdapInitialCtxFactory.

Valid value: See LdapInitialCtxFactory.

Default value is "".

### **BackupLdapSecurityAuthentication**

This parameter denotes the backup LDAP server's security authentication protocol. See LdapSecurityAuthentication.

Valid value: See LdapSecurityAuthentication.

Default value is "simple".

---

## LdapUserClassTop

LdapUserClassTop/LdapUserClassPerson/LdapUserClassOrganizationalPerson/Ldap

UserClassInetOrgPerson store the four object classes used to assign various attributes to any user information stored in an LDAP-provider. These objectClasses are used to assign almost any attributes of the user and are defined by default in the schema of the LDAP-provider. Please note that - When creating a new LDAP entry, you must always specify all of the object classes to which the new entry belongs. Because many directories do not support object class subclassing, you also should always include all of the superclasses of the entry. For example, for an "organizationalPerson" object, you should list in its object classes the "organizationalPerson", "person", and "top" classes.

Valid value: This parameter takes input any valid object class name.

Default value is "top".

## LdapUserClassPerson

See LdapUserClassTop.

Valid value: This parameter takes input any valid object class name.

Default value is "Person".

## LdapUserClassOrganizationalPerson

See LdapUserClassTop.

Valid value: This parameter takes input any valid object class name.

Default value is "OrganizationalPerson".

## LdapUserClassInetorgPerson

See LdapUserClassTop.

Valid value: This parameter takes input any valid object class name.

Default value is "inetOrgPerson".

## LdapGroupClassTop

LdapGroupClassTop and LdapGroupClassUniqueNames store the two object classes used to assign various attributes to a Group that are defined in the schema of the LDAP-provider. When creating a new LDAP entry, you must always specify all of the object classes to which the new entry belongs. Because many directories do not support object class subclassing, you also should always include all of the superclasses of the entry. For example, for an "organizationalPerson" object, you should list in its object classes the "organizationalPerson", "person", and "top" classes.

---

Valid value: This parameter takes input any valid object class name.

Default value is "top".

### **LdapGroupClassUniqueNames**

See LdapGroupClassTop.

Valid value: This parameter takes input any valid object class name.

Default value is "groupofuniquenames".

### **LdapGroupClassUniqueMember**

This value is used to initialize the attribute "uniquemember", of a Group entry, which is used when adding new users to the Group or querying for the members of a group. Suppose it can take the value : cn=something,o=fiorano,c=us. Generally, we assign the value of "LdapProviderDn" which is o=fiorano,c=us by default, for this.

Valid value: LdapGroupClassUniqueMember can take any valid value which can be given as a proper Relative Distinguished Name (RDN).

Default value is "o=fiorano,c=US".

### **LdapUserNameAttribute**

The value of this field can be the common name of an LDAP user (cn), but usually it is an abbreviated string, such as User ID (uid) since we are storing the unique user-identities in LDAP-provider. In that case, the full Distinguished name (DN) for an entry in LDAP structure will be uid=admin,cn=FioranoMQUsers,o=fiorano,c=US.

Valid value: This parameter takes input provider specific valid common name.

Default value is "uid".

### **LdapUserPasswordAttribute**

Attribute ID for the password attribute for the FioranoMQ user stored as a LDAP named object.

Valid value: This parameter takes input provider specific valid common name.

Default value is "userpassword".

### **LdapGroupNameAttribute**

Attribute ID for the group name attribute for the FioranoMQ group stored as a LDAP named object.

Valid value: This parameter takes input provider specific valid common name.

---

Default value is "cn".

### LdapGroupUserNameAttribute

Attribute ID for the user name attribute stored in a group which is stored as a LDAP named object.

Valid value: This parameter takes input provider specific valid common name.

Default value is "uniquemember".

### LdapUserDn

Relative distinguished name of an LDAP entry, under the entry specified by the parameter 'LdapProviderDn', under which the FioranoMQ users' information is stored.

Valid value: This parameter takes input any RDN of an existing LDAP entry under LdapProviderDn.

Default value is "cn=FioranoMQUsers".

### LdapGroupDn

Relative distinguished name of an LDAP entry, under the entry specified by the parameter 'LdapProviderDn', under which the FioranoMQ groups' information is stored.

Valid value: This parameter takes input any RDN of an existing LDAP entry under LdapProviderDn.

Default value is "cn=FioranoMQGroups".

## XMLFilePrincipalManager

Following are the parameters present in Fiorano->security->PrincipalManager->XMLFilePrincipalManager

### Path

String representing directory path where user information will be stored in XML format.

**Default Value:** realm/principal

### UserFilename

XML File name that contains user information in String format

**Default Value:** user.xml - The default xml filename

---

## GroupFilename

XML File name that contains Group information in String format

**Default Value:** group.xml – The default xml file name

## PrincipalManagerRDBMS

Following are the parameters present in Fiorano->security->PrincipalManager->PrincipalManager.RDBMS

### Url

String representing database URL where user/group information will be store.

**Example:** jdbc:oracle:thin:@localhost:1521:ORCL for oracle server

### Password

Password for RDBMS User in String format- Used for connecting to the RDBMS Server

### Username

Database User Name in String format- Used for connecting to the RDBMS Server.

**Default Value:** sa

### DBDriver

String value of JdbcDriver used for RDBMS based datastorage.

**Default Value:** org.hsqldb.jdbcDriver - The default database driver class name

### ConnectionTimeoutInterval

Integer representing database connection open timeout

**Default Value:** 10000 - The time in milliseconds for connection timeout

**Valid Value:** Non negative Integer with value zero representing wait forever

### ReconnectTimeInterval

Integer representing Time interval (in msec) between two reconnect attempts in disconnected state.

---

**Default Value:** 10000 – The time in milliseconds taken by Principal Manager between reconnect attempts

**Valid Value:** Non negative Integer

### EnableReconnect

Boolean value which specifies if Principal Manager has to try to reconnect to database server in case of a connection breakup

**Valid Values:**

- True - Enables reconnect attempts to database server when the connection is down.
- False - Disables reconnect attempts to database server when the connection is down.

**Default Value:** True - Enables reconnect attempts to database server when the connection is down.

### StatementFile

String representing Sql statement file which contains the SQLs used by PrincipalManager for Database operations.

**Default Value:** principalsqlstatements.properties - The default properties used which is located at %FIORANO\_HOME%/fmq/profiles/%YOUR\_PROFILE%/conf

### ConnectionLostErrorMessage

String representing Error message to be posted in case of lost connection

Allows the user to set the custom messages to be displayed when connection to the RDBMS server is lost

**Default Value:** DB\_CONNECTION\_LOST - The default connection lost message.

### InitializeDB

Boolean value to enable/disable the initialization of the underlying Database by creating necessary tables on startup if required

**Valid values:**

- True- Enables initializing the DB
- False - Disables initializing the DB

**Default Value:** True - Enables initializing the DB.

---

## FileDBManager2

Presented below are the details of the parameters in **FioranoMQ->Fiorano->Security->PrincipalManager->FileDBManager->FileDBManager2**.

### Path

The security configuration for the principal is stored in the file based data storage specified by the Path parameter.

#### Valid value:

The default value of the Path parameter is **SDB/REALM.PRINCIPAL**

The path specified is relative to the run directory of each **FioranoMQ** profile.

### DeletedThresholdPercent

A cache stores and manages the list of all tables pertaining to principal as well as all related information in the file-storage table. After repeated modification of the table, old entries in the table are marked as deleted. This value provides a threshold percentage of deleted entries after which the Cache Compaction Process is invoked. At the end of the Cache Compact Process the table will not have any deleted entries. Since cache compaction involves CPU intensive File Operations, this flag is to be used along with DeletedThresholdCount to ensure it is not invoked too often.

#### Valid value:

The default value of the DeletedThresholdPercent is 50. This indicates that if the ratio of deleted entries to total entries is equal to or greater than 0.5 the Cache compaction process is invoked.

#### Note:

- The range of integer values in java considered valid by the DeletedThresholdPercentage value are  $-2^{32}$  to  $2^{32} - 1$ .
- All values less than or equal to zero provide the same result.
- All values greater than or equal to 100 provide the same result.

#### Example:

Use an example ratio of deleted entries/total entries in the table. If there is good chance that many entries will be marked as deleted then it is best to choose a higher number.

---



## DeletedThresholdCount

A cache stores and manages the list of all tables pertaining to the principal as well as all related information in the file-storage table. After repeated modification of the table, old entries in the table are marked as deleted. This value provides a threshold count of deleted entries for starting the Cache Compaction Process. At the end of the Cache Compact Process the table will not have any deleted entries. Since cache compaction involves CPU intensive File Operations, this flag is to be used along with DeletedThresholdPercent to ensure it is not invoked too often.

### Valid value:

The default value of the DeletedThresholdCount is **10**.

The range of integer values considered valid for the DeletedThresholdCount parameter in java are  $-2^{32}$  to  $2^{32} - 1$ .

All values less than or equal to zero provide the same result.

### Example:

Although the DeleteThresholdPercent provides a ratio based method of ensuring that the Cache Compaction Process does not occur too often, it does not provide an absolute lower limit of the number of deleted entries needed to trigger a Cache Compaction. A value high enough to trigger a Cache Compaction should be chosen.

## DbTableNamePrefix

The database table names prefixed with a string can be modified by the DbTableNamePrefix parameter.

### Valid value:

The default value of the DbTableNamePrefix is **#**.

Any String value is a valid parameter.

### Example:

If the database table is to be saved in its current state and the the current state is to be saved to be used in the future, modify the prefix to another relevant string and change it back to the original string when the saved state of the database table is to be used.

# Chapter 10: Logger Configuration

---

This chapter explains the configurable parameters related to the FioranoMQ Logger module (i.e., related to server logs or monitoring logs or dashboard logs) in the server.

For information on how to configure FioranoMQ Server Loggers in Offline and online mode, refer to **Chapter 20 Logger** of *FioranoMQ Handbook*.

## Introduction


Logging into FioranoMQ is achieved with the help of Log4J which makes it is possible to log in at runtime without modifying the application binaries. All log entries are logged at particular log levels. Each logger is given a logging level. The various logger levels are given below.

Value	Logger	Description
-1	INHERIT	Inherits log level from its parent
0	QUIET	No logged information
1	FATAL	Severe errors that might cause premature termination
2	ERROR	Other runtime errors or unexpected conditions
3	WARN	Use of deprecated APIs, poor use of API, <b>almost</b> errors, other runtime situations that are undesirable or unexpected but not necessarily "wrong".
4	INFO	Interesting runtime events (startup/shutdown)
5	DEBUG	Detailed information on the flow through the system
6	TRACE	More detailed information
10	ALL	All logged information

**Table 1: Log levels**

These values are defined so that if given a value **x**, all entries logged with a value less than or equal to **x** will be received by the logger.

- [-] Fiorano
  - [-] FMQ
    - [-] Services
      - Gms
      - FmqConnectionManagerServices
      - JobManager
      - Operations
    - + Topics
      - Cbr
      - Rdbms
      - PubSubSlowdown
      - PurgeDeliveredPersistentMessages
      - SocketRead
    - + Queues
      - LogError
      - Realm
      - ConnectionCreation
      - FmqAdminServices
    - [-] Events
      - ResourceManager
      - Queue
      - Dmq
      - TopicPublisher
      - Tcf
      - QueueReceiver
      - Qcf
      - QueueSender
      - TopicConnection
      - QueueConnection
      - TopicSubscriber
      - Topic
  - Monitoring



**Figure 1: Loggers in hierarchical manner**

Loggers are arranged hierarchies depicting parent-child relationships. Each element in the tree (Figure 1) has these two attributes as shown Figure 2, below:

Edit Logger Properties	
Name	Fiorano.FMQ.Services.PurgeDeliveredPersistentMessages
EffectiveLogLevel	3
LogLevel	Inherit
AppenderAdditive	true
<input type="button" value="OK"/> <input type="button" value="Cancel"/>	

**Figure 2: Edit Logger Properties dialog box**

The log level parameter of the loggers can be set to any one of the values present in Table 1. The information present in the log files will depend on the value set. Some examples using the logger configurations are given below:

- If the 'Log Level' attribute of Fiorano.Services.Topics.MsgFlow.Message is set to trace (6), all the messages published to a topic along with its corresponding properties are logged.
- If the 'Log Level' attribute of Fiorano.Services.Topics.MsgFlow.Publish is set to trace (6), the life cycle of the message, in its various stages of sending, is logged.
- If the 'Log Level' attribute of Fiorano.Services.Queues.Push.Message is set to trace (6), all messages sent to a queue along with its corresponding properties are logged.
- If the 'Log Level' attribute of Fiorano.Services.Queues.Pop is set to trace (6), the life cycle of the message, after it is pushed into the queue, is logged.
- If the 'Log Level' attribute of Fiorano.Services.Topics.MsgFlow.Message is set to trace (6), all the messages published to a topic along with its corresponding properties are logged.
- If the 'Log Level' attribute of Fiorano.Events.TopicPublisher is set to trace (6), all publisher events such as **open** and **close** are logged.
- If the 'Log Level' attribute of Fiorano.Events.QueueReceiver is set to trace (6), all receiver events such as **open** and **close** are logged.
- If the 'Log Level' attribute of Fiorano.Services.Jmx.Operations is set to trace (6), details of all Jmx operations are logged.

If the 'Log Level' attribute of Fiorano.Services.Jmx.Attributes is set to trace ( 6), the details of all attributes accessed using Jmx connections are logged.

## AppenderAdditive

AppenderAdditive specifies the Appender Additivity for the logger. The output of a log statement of logger, say **C**, will go to all appenders and ancestors of **C**. However, if an ancestor of logger **C**, say **P**, has the additivity flag set to false, then C's output will be directed to all the appenders in C as well as to all ancestors up to and including P but not to the appenders of the ancestors of **P**.

### Valid value:

The default value for the AppenderAdditive parameter is **yes**

- **yes** - Logging output of present element will be directed to its parent.
- **no** - Logging output of present element will not be directed to its parent.

## LogLevel

LogLevel is the level of logging. No log event will be generated for a logging statement above this level.

---

**Valid value:**

The default value for the LogLevel is **-1**.

Legal values: -1 to 6. (Refer to table 1, above, for more information.)

## LogAppender

Presented below are the details of the parameters in **Fiorano->config->LogAppender**

### AppenderName

The AppenderName parameter provides a unique Appender Name.

**Valid value:**

The default value is of the AppenderName parameter is **LogAppender**.

Any String

### AppenderType

AppenderType is a parameter that specifies the type of appender to be used. A LogAppender type, for example, decides on the endpoint set to receive logging information.

**Valid value:**

The default value for the AppenderType parameter is file.

- **file** - the appender in use will be a **file** type. Log messages will be written to a file.
- **console** - the appender in use will be a **console** type. Log messages will be written to the console.

**Example:**

When logged messages qualify, or are important enough, to be displayed on the console, the AppenderType of the console will need to be changed from its file value.

## LogPattern

The LogPattern parameter specifies the Log4J format for printing logs. (Please refer to Log4J documentation for more details.)

**Valid value:**

The default value for the LogPattern Parameter is **[%d{dd/MMM/yyyy HH:mm:ss}] %-10c{1} %-10p %m%n**

---

**Example:**

{%F, %M} %-5p [%c{1}] %m%n will print CodeFileName, MethodName when the log event is generated.

## ThresholdLevel

The ThresholdLevel parameter indicates that log events logged above this ThresholdLevellog level will not be received/logged by the Appender.

**Valid value:**

The default value of the ThresholdLevel parameter is 10.

The range of integer values in java for the ThresholdLevel parameter are  $-2^{32}$  to  $2^{32} - 1$ .

**Note:**

- All values less than or equal to zero retrieve the same result..
- All values greater than or equal to 10 retrieve the same result.

## FilterPattern

The FilterPattern is a regex based string filter pattern for filtering log events received by the Appender. Only Events which matches the filter criteria are logged.

**Valid value:**

The default value for the FilterPattern parameter is null.

- Any valid regex expression may be used.
- null - all strings are accepted by a null regular expression.

**Example:**

When only the messages that match the criteria defined by the regex are to be logged, the regular expression is to be set.

## PrintTarget

The PrintTarget parameter is applicable only to console appenders and the print target can be chosen to reflect the target that the console output prints to.

**Valid value:**

The default value for the PrintTarget parameter is System.out.

For a value set in the PrintTarget field to have any effect the AppenderType should be set console.

---

- **System.out** - When appendertype is set to console the console output will print to the standard output stream.
- **System.err** - When appendertype is set to console the console output will print to the standard error output stream.

## FileName

The FileName parameter is the name of the log file to which the log events are logged when the AppenderType is **file**.

### Valid value:

The values considered valid by the FileName parameter are can be any valid filename. The default value of this parameter is **server.log**

When a relative path for a filename is given a log file is created in **<current-profile>/run/logs/**. If an absolute path for a filename is given a log file is created in its corresponding directory.

## IsAppend

The IsAppend parameter option is useful only when the AppenderType is specified as a **file** type. When the server boots and a log file that is specified already exists, this parameter specifies whether the log file that exists overwritten or if the log entries are appended to the existing file.

### Valid value:

The default value for the IsAppend Parameter is **yes**

- **yes** - Log entries are appended to the existing log file.
- **no** - The existing log file is overwritten by the new entries.

## MaxBackupIndex

The MaxBackupIndex parameter specifies whether the type of FileAppender used by **FioranoMQ** is a **RollingFileAppender**. The RollingFileAppender can be used to roll log files based on size. When the **FileSize** exceeds **MaxFileSize** the log file will be **rolled**. Rolling consists of the creation of a new log file with an incremental index appended to its filename. The MaxBackupIndex parameter helps specify the maximum number of such files to be created. Example: A **2** will have at most 3 log files. **file.log, file1.log, file2.log**. This parameter may be used only when the **AppenderType** used is file.

### Valid value:

The default value for the MaxBackupIndex parameter is **9**.

The range of integer values in java for the MaxBackupIndex parameter are  $-2^{32}$  to  $2^{32} - 1$ .

---



All values less than or equal to zero retrieve the same result.

### Dependencies

Please refer to MaxFileSize and to AppenderType.

### MaxFileSize

The MaxFileSize parameter specifies the maximum size of a log file in bytes. Once the maximum size specified is reached the log file is rolled. (For an explanation on RollingFileAppender, refer to **MaxBackupIndex**.) This parameter may be used when the **AppenderType** is a **file**.

#### Valid value:

The default value for the MaxFileSize parameter is 5000000.

Legal values: range of int values in java. ( $-2^{32}$  to  $2^{32} - 1$ )  
All values less than or equal to zero are as good as each other.

### Dependencies

Please refer to MaxBackupIndex and to AppenderType.

### MaxFilterLevel

The MaxFilterLevel parameter specifies the Maximum Filter level for log events. Events logged above the log level specified by this parameter will not be received/logged by the Appender.

#### Valid value:

The range of integer values considered valid for the MaxFilterLevel parameter in java are -  $2^{32}$  to  $2^{32} - 1$ . The default value of this parameter is **10**.

All values less than or equal to zero retrieve the same result.

### MinFilterLevel

The MinFilterLevel parameter specifies the Minimum Filter level for log events. Events logged below the log level specified by this parameter will not be received/logged by the Appender.

#### Valid value:

The range of integer values considered valid in java for the MinFilterLevel parameter are -  $2^{32}$  to  $2^{32} - 1$ . The default value for this parameter is **1**.

All values less than or equal to retrieve the same result.

---

## LogAppender

**Monitoring->config->LogAppender**

### AppenderName

The AppenderName parameter provide a unique Appender Name.

#### Valid value:

Any String. The default value for the AppenderName parameter is **LogAppender**.

### AppenderType

The AppenderType parameter specifies the type of appender to be used. The **LogAppender Type** decides the endpoint that will receive the logging information.

#### Valid values:

The default value for the AppenderType is **file**.

- **file** - the appender used will be of the **file** type. Log messages will be written to the file.
- **console** - the appender used will be of the **console** type. Log messages will be written to the console.

#### Example:

When the logged messages qualify or are important enough to be displayed on the console, the AppenderType to console must be changed from its default value of **file**.

### LogPattern

The LogPattern parameter specifies the Log4J format for printing logs. (Please refer to Log4J documentation for more details.)

#### Valid value:

The default value of the LogPattern is **[%d{dd/MMM/yyyy HH:mm:ss}] %-10c{1} %-10p %m%n**

#### Example:

**[{%F, %M} %-5p [%c{1}] %m%n]** will print CodeFileName and MethodName when the log event is generated.

### ThresholdLevel

Log events logged above the ThresholdLevel parameter of the log level will not be received/logged by the Appender.

---

**Valid values:**

The range of integer values that are considered valid by the ThresholdLevel Parameter in java are  $-2^{32}$  to  $2^{32} - 1$ . The default value for this parameter is 10.

**Note:**

- All values less than or equal to zero retrieve the same result.
- All values greater than or equal to 10 retrieve the same result.

**FilterPattern**

The FilterPatter parameter is a regex based string filter pattern for filtering log events received by the Appender. Only events which matches the filter criteria are logged.

**Valid values:**

The default value for the FilterPattern is null. Values considered valid by this parameter include all valid regex expression.

**Null** - all strings are accepted by a null regular expression.

**Example:**

When only the messages that match the criteria defined by the regex are to be logged, the appropriate regular expression needs to be set.

**PrintTarget**

The PrintTarget parameter is applicable only to console appenders. The print target can be chosen to reflect the target the console output is to be printed to.

**Valid values:**

The default value is of the PrintTarget parameter is **System.out**.

For this parameter to work, the **AppenderType** should be set to **console**.

- **System.out** - When appendertype is set to console, the console output is printed to the standard output stream.
- **System.err** - When appendertype is set to console, the console output is printed to the standard error output stream.

**Dependencies:**

AppenderType

**FileName**

The FileName parameter specifies the name of the log file to which the log events are logged if the AppenderType is a **file**.

---

**Valid values:**

The default value of the FileName is **server.log**

Any valid filename is considered a valid value by the FileName parameter.

If a relative path for a filename is given, the log file is created in the directory relative to the file name specified: <current-profile>/run/logs/.if an absolute path for a filename is given, the log file is created in its corresponding directory.

**Dependencies:**

AppenderType

**IsAppend**

The IsAppend parameter is used only when the AppenderType is specified as **file**. If the log file specified already exists, this option specifies whether this log file will be overwritten or whether the log entries will be appended.

**Valid values:**

The default value of the IsAppend parameter is **yes**.

- **yes** - Log entries are appended to the existing log file.
- **no** - The log file is overwritten by the new entries.

**MaxBackupIndex**

The MaxBackupIndex parameter specifies whether the **type** of **FileAppender** used by FioranoMQ is a RollingFileAppender. The RollingFileAppender can be used to roll log files based on size. When the filesize exceeds MaxFileSize the log file will be rolled. A new log file will be created which will have an incremental index appended to its filename. This parameter helps specify the maximum number of files to be created and will have at most 3 log files: file.log, file1.log, file2.log. This may be used only when the **AppenderType** is a **file**.

**Valid values:**

The range of integer values considered valid by this parameter in java are  $-2^{32}$  to  $2^{32} - 1$ . The default value of this parameter is **4**.

All values less than or equal to zero retrieve the same result.

**Dependencies:**

MaxFileSize and AppenderType.

---

## MaxFileSize

The MaxFileSize parameter specifies the maximum size of a log file in bytes. Once a log file reaches this size it is rolled (For an explanation on RollingFileAppender see MaxBackupIndex.) This parameter may be used only when the AppenderType is a **file**.

### Valid values:

The range of integer values considered valid by the MaxFileSize parameter in java are  $-2^{32}$  to  $2^{32} - 1$ . The default value of this parameter is **1000000**

All values less than or equal to zero retrieve the same results.

### Dependencies:

MaxBackupIndex and AppenderType.

## MaxFilterLevel

The MaxFilterLevel parameter specifies the maximum filter level for log events. Events logged above this log level will not be received/logged by the Appender.

### Valid values:

The range of integer values considered valid by the MaxFilterLevel parameter in java are  $-2^{32}$  to  $2^{32} - 1$ . The default value for this parameter is **10**.

All values less than or equal to zero retrieve the same result.

## MinFilterLevel

The MinFilterLevel parameter specifies the minimum filter level for log events. Events logged below this log level will not be received/logged by the Appender.

### Valid values:

The range of integer values that are considered valid by the MinFilterLevel parameter in java are  $-2^{32}$  to  $2^{32} - 1$ . The default value for this parameter is **1**

All values less than or equal to zero retrieve the same result.

---

# Chapter 11: HA Replicated Configuration

---

This chapter explains the parameters that can be configured for FioranoMQ Servers running in Replicated High Availability mode. These are the various parameters that are configured under the FioranoMQ→Fiorano→HA→\* tree node in Replicated HA Profiles in Offline configuration using Studio.

For more information on High Availability, refer to the *FioranoMQ High Availability Guide*

## Primary Server Configuration

### FioranoHAConnectionManager

Presented below are the details for the parameters in **Fiorano->HA->HAConnectionManager->FioranoHAConnectionManager->config**.

#### Port

The Port parameter specifies the port on which the HA Manager listens on for connections from the peer HA Server. This parameter listens for a connection from HA Peer Server in order to know the status of its peer.

#### Valid values:

The default value of the Port parameter is **2000**.

The range of integer values considered valid by the Port parameter in java are  $-2^{31}$  to  $2^{31}-1$ .

**Note:** The port may not be used by other services when being used to listen to Peer servers..

#### NagleAlgo

The NagleAlgo parameter is a doolean value that determines whether Nagle's Algorithm is enabled during socket creation with peer HA Server. Nagle's algorithm is used in TCP/IP networks for congestion control. It works by coalescing a number of small outgoing messages and sending them together, all at once. If there is a **sent packet** for which the sender has received no acknowledgment, the sender should keep buffering its output until it has a full packet worth of output, so as to send the entire output in one go.

#### Valid values:

The default value for the NagleAlgo parameter is **no**.

- **yes** – Indicates that the NagleAlgo is enabled.

- **no** – Indicates that the NagleAlgo is not enabled.

#### **Example:**

The Nagle algorithm should not be enabled in situations involving **Delayed ACK** as that will cause TCP performance problems.

#### **SocketInitializationTimeout**

The SocketInitializationTimeout parameter indicates the time in milliseconds within which a client socket should identify itself and exchange its version number with the Server. The version number exchange is an authentication mechanism that FioranoMQ employs.

#### **Valid values:**

The default value for the SocketInitializationTimeout parameter is **60000** (which is equal to one minute).

The range of integer values considered valid by the SocketInitializationTimeout parameter in java are  $-2^{31}$  to  $2^{31} - 1$ .

All values less than zero retrieve the same result.

#### **QGMSSubManager**

Presented below are the details for the parameters in **Fiorano->HA->HAConnectionManager->HAServiceManager->HSubSystems->QGMSSubManager**.

#### **MinServiceID**

The MinServiceID parameter defines a serviceID in FioranoMQ with each request associated with a subsystem. The range of serviceIDs associated with a subsystem defines the operations that are accessible to that subsystem. The MinServiceID defines the minimum value of the range that exists for the serviceIDs.

#### **Valid values:**

The default value of the MinServiceID parameter is null. If the value is specified as null, there is no range defined for the serviceIDs.

The range of integer values considered valid by the MinServiceID in java are  $-2^{31}$  to  $2^{31} - 1$ .

All values less than zero retrieve the same result.

---

## MaxServiceID

The MaxServiceID parameter defines a serviceID in FioranoMQ. Each request is associated with a subsystem. A range of serviceIDs associated with a subsystem determine the operations accessible to the subsystem. The MaxServiceID defines the maximum value of the range that exists for the serviceIDs.

### Valid values:

The default value for the MaxServiceID parameter is null. If the value is specified as null, there is no range defined for the serviceIDs. The range of integer values considered valid by the MaxServiceID in java are  $-2^{31}$  to  $2^{31} - 1$ . All values less than zero retrieve the same result.

## TGMSStubManager

Presented below are the details for the parameters in **Fiorano->HA->HAConnectionManager->HAServiceManager->HSubSystems->TGMSStubManager**.

## MinServiceID

The MinServiceID parameter defines a serviceID in FioranoMQ. Each request is associated with a subsystem. A range of serviceIDs associated with a subsystem determine the operations accessible to the subsystem. The MinServiceID defines the minimum value of the range that exists for the serviceIDs.

### Valid values:

The default value of the MinServiceID parameter is null. If the value is specified as null, there is no range defined for the serviceIDs. The range of integer values considered valid by the MinServiceID in java are  $-2^{31}$  to  $2^{31} - 1$ . All values less than zero retrieve the same result.

## MaxServiceID

The MaxServiceID parameter defines a serviceID in FioranoMQ. Each request is associated with a subsystem. A range of serviceIDs associated with a subsystem determine the operations accessible to the subsystem. The MaxServiceID defines the maximum value of the range that exists for the serviceIDs.

### Valid values:

The default value for the MaxServiceID parameter is null. If the value is specified as null, there is no range defined for the serviceIDs.

The range of integer values considered valid by the MaxServiceID in java are  $-2^{31}$  to  $2^{31} - 1$ .

All values less than zero retrieve the same result.

---



## SyncRealmStubManager

Presented below are the details for the parameters in **Fiorano->HA->HAConnectionManager->HServiceManager->HSubSystems->SyncRealmStubManager**.

### MinServiceID

The MinServiceID parameter defines a serviceID in FioranoMQ. Each request is associated with a subsystem. A range of serviceIDs associated with a subsystem determine the operations accessible to the subsystem. The MinServiceID defines the minimum value of the range that exists for the serviceIDs.

#### Valid values:

The default value of the MinServiceID parameter is null. If the value is specified as null, there is no range defined for the serviceIDs..

The range of integer values considered valid by the MinServiceID in java are  $-2^{31}$  to  $2^{31} - 1$ . All values less than zero retrieve the same result.

### MaxServiceID

The MaxServiceID parameter defines a serviceID in FioranoMQ. Each request is associated with a subsystem. A range of serviceIDs associated with a subsystem determine the operations accessible to the subsystem. The MaxServiceID defines the maximum value of the range that exists for the serviceIDs.

#### Valid values:

The default value for the MaxServiceID parameter is null. If the value is specified as null, there is no range defined for the serviceIDs. The range of integer values considered valid by the MaxServiceID in java are  $-2^{31}$  to  $2^{31} - 1$ . All values less than zero retrieve the same result.

## SyncNamingStubManager

Presented below are the details for the parameters in **Fiorano->HA->HAConnectionManager->HServiceManager->HSubSystems->SyncNamingStubManager**.

### MinServiceID

The MinServiceID parameter defines a serviceID in FioranoMQ. Each request is associated with a subsystem. A range of serviceIDs associated with a subsystem determine the operations accessible to the subsystem. The MinServiceID defines the minimum value of the range that exists for the serviceIDs.

---

**Valid values:**

The default value of the MinServiceID parameter is null. If the value is specified as null, there is no range defined for the serviceIDs. The range of integer values considered valid by the MinServiceID in java are  $-2^{31}$  to  $2^{31} - 1$ . All values less than zero retrieve the same result.

**MaxServiceID**

The MaxServiceID parameter defines a serviceID in FioranoMQ. Each request is associated with a subsystem. A range of serviceIDs associated with a subsystem determine the operations accessible to the subsystem. The MaxServiceID defines the maximum value of the range that exists for the serviceIDs.

**Valid values:**

The default value for the MaxServiceID parameter is null. If the value is specified as null, there is no range defined for the serviceIDs. The range of integer values considered valid by the MaxServiceID in java are  $-2^{31}$  to  $2^{31} - 1$ . All values less than zero retrieve the same result.

**NamingStubManager**

Presented below are the details for the parameters in **Fiorano->HA->HAConnectionManager->HAServiceManager->HSubSystems->NamingStubManager**

**MinServiceID**

The MinServiceID parameter defines a serviceID in FioranoMQ. Each request is associated with a subsystem. A range of serviceIDs associated with a subsystem determine the operations accessible to the subsystem. The MinServiceID defines the minimum value of the range that exists for the serviceIDs.

**Valid values:**

The default value of the MinServiceID parameter is null. If the value is specified as null, there is no range defined for the serviceIDs. The range of integer values considered valid by the MinServiceID in java are  $-2^{31}$  to  $2^{31} - 1$ .

All values less than zero retrieve the same result.

**MaxServiceID**

The MaxServiceID parameter defines a serviceID in FioranoMQ. Each request is associated with a subsystem. A range of serviceIDs associated with a subsystem determine the operations accessible to the subsystem. The MaxServiceID defines the maximum value of the range that exists for the serviceIDs.

---

**Valid values:**

The default value for the MaxServiceID parameter is null. If the value is specified as null, there is no range defined for the serviceIDs. The range of integer values considered valid by the MaxServiceID in java are  $-2^{31}$  to  $2^{31} - 1$ . All values less than zero retrieve the same result.

## SyncQueueStubManager

Presented below are the details for the parameters in **Fiorano->HA->HAConnectionManager->HServiceManager->HSubSystems->SyncQueueStubManager**

### MinServiceID

The MinServiceID parameter defines a serviceID in FioranoMQ. Each request is associated with a subsystem. A range of serviceIDs associated with a subsystem determine the operations accessible to the subsystem. The MinServiceID defines the minimum value of the range that exists for the serviceIDs.

**Valid values:**

The default value of the MinServiceID parameter is null. If the value is specified as null, there is no range defined for the serviceIDs. The range of integer values considered valid by the MinServiceID in java are  $-2^{31}$  to  $2^{31} - 1$ . All values less than zero retrieve the same result.

### MaxServiceID

The MaxServiceID parameter defines a serviceID in FioranoMQ. Each request is associated with a subsystem. A range of serviceIDs associated with a subsystem determine the operations accessible to the subsystem. The MaxServiceID defines the maximum value of the range that exists for the serviceIDs.

**Valid values:**

The default value for the MaxServiceID parameter is null. If the value is specified as null, there is no range defined for the serviceIDs. The range of integer values considered valid by the MaxServiceID in java are  $-2^{31}$  to  $2^{31} - 1$ . All values less than zero retrieve the same result.

## RpStateStubManager

Presented below are the details for the parameters in **Fiorano->HA->HAConnectionManager->HServiceManager->HSubSystems->RpStateStubManager**.

---

## MinServiceID

The MinServiceID parameter defines a serviceID in FioranoMQ. Each request is associated with a subsystem. A range of serviceIDs associated with a subsystem determine the operations accessible to the subsystem. The MinServiceID defines the minimum value of the range that exists for the serviceIDs.

### Valid values:

The default value of the MinServiceID is 2001.

The range of integer values considered valid by the MinServiceID in java are  $-2^{31}$  to  $2^{31} - 1$ . All values less than zero retrieve the same result.

## MaxServiceID

FioranoMQ defines a serviceID with each request associated with a subsystem and thus the range of serviceIDs that are associated with a subsystem defines the operations that are accessible to that subsystem. This value defines the maximum value of that range.

### Valid values:

The default value of the MaxServiceID is 3000.

The range of integer values considered valid by the MaxServiceID in java are  $-2^{31}$  to  $2^{31} - 1$ . All values less than zero retrieve the same result.

## FioranoRpRealmManager

Presented below are the details for the parameters in **Fiorano->HA->ReplicableRealmMgr->RpRealmManager->FioranoRpRealmManager->config**

## AclZipPath

In the Replicable mode of the FioranoMQ HA Server, consistency between the individual HA Servers must be maintained at all times. In order to be able to synchronize realm related (ACL based) information a zip file containing the ACL information present in this server must be created. The AclZipPath parameter allows the configuration of the path where this file is located.

### Valid values:

The default value of the AclZipPath is **fmq\_acl.zip**.

Any valid filename for a zip file may be used for this parameter.

Given a relative path for a zip file name, the zip file is created relative that path in the directory: **<current-profile>/run/**. If its an absolute path for a file name is given, the zip file is created in that directory.

---

## AclUnzipDir

In the Replicable mode of the FioranoMQ HA Server, consistency between the individual HA Servers must be maintained at all times. In order to be able to synchronize realm related (ACL based) information a zip file is created using the ACL information. The AclUnzipDir parameter allows the configuration of the path where the zip file is temporarily unzipped.

### Valid values:

The default value of the AclUnzipDir parameter is **ACL\_TEMP**.

Any valid filename may be used for this parameter.

Given a relative path for a zip file name, the zip file is created relative that path in the directory: <current-profile>/run/. If its an absolute path for a file name is given, the zip file is created in that directory.

## PrincipalZipPath

In the Replicable mode of the FioranoMQ HA Server, consistency between the individual HA Servers must be maintained at all times. In order to be able to synchronize principal related (User based) information a zip file is created using the information related to the principal present in the Server. The PrincipalZipPath parameter allows the configuration of the path in where this file is located.

### Valid values:

The default value of the PrincipalZipPath parameter is **fmq\_principal.zip**.

Any valid filename for a zip file may be used for this parameter.

Given a relative path for a zip file name, the zip file is created relative that path in the directory: <current-profile>/run/. If its an absolute path for a file name is given, the zip file is created in that directory.

## PrincipalUnzipDir

In the Replicable mode of the FioranoMQ HA Server, consistency between the individual HA Servers must be maintained at all times. In order to be able to synchronize principal related (User based) information a zip file is created using the information related to the principal. The PrincipalUnzipDir parameter allows the configuration of the path where this zip file is temporarily unzipped.

### Valid values:

The default value of the PrincipalUnzipDir parameter is **PRINCIPAL\_TEMP**.

Any valid filename may be used for this parameter.

Given a relative path for a zip file name, the zip file is created relative that path in the directory: <current-profile>/run/. If its an absolute path for a file name is given, the zip file is created in that directory.

---

## SocketTimeout

The SocketTimeout parameter indicates the time in milliseconds before the socket times out for this replicable component occurs. Replication of the principal and realm related information must be done within this time.

### Valid values:

The default value of the SocketTimeout parameter is **240000** (equal to four minutes).

The range of integer values considered valid by the SocketTimeout parameter are  $-2^{31}$  to  $2^{31} - 1$

All values less than zero retrieve the same result.

## FioranoRpNamingManager

Presented below are the details of the parameters in **Fiorano->HA->ReplicableNamingMgr->RpNamingManager->FioranoRpNamingManager->config**.

## ZipPath

In the Replicable mode of the FioranoMQ HA Server, consistency between the individual HA Servers must be maintained at all times. In order to be able to synchronize name related information a zip file using naming related information present in the Server is created. The ZipPath parameter allows the configuration of the path where this file is located.

### Valid values:

The default value of the ZipPath parameter is **fmq\_nmdb.zip**.

Any valid file name for a zip file may be used for this parameter.

Given a relative path for a zip file name, the zip file is created relative that path in the directory: **<current-profile>/run/**. If its an absolute path for a file name is given, the zip file is created in that directory.

## UnzipDir

In the Replicable mode of the FioranoMQ HA Server, consistency between the individual HA Servers must be maintained at all times. In order to be able to synchronize name related information, a zip file using naming related information is created. The UnzipDir parameter allows the configuration of the path where the zip file is temporarily unzipped.

### Valid values:

The default value for the UnzipDir parameter is **NM\_TEMP**.

Any valid filename may be used for this parameter.

---

Given a relative path for a zip file name, the zip file is created relative that path in the directory: **<current-profile>/run/**. If its an absolute path for a file name is given, the zip file is created in that directory.

### SocketTimeout

The SocketTimeout parameter indicates the time in milliseconds before the socket times out for this replicable component occurs. Replication of all naming related information must be done within this time.

#### Valid values:

The default value for the SocketTimeout parameter is **240000** (equal to four minutes).

The range of integer values considered valid by the SocketTimeout are  $-2^{31}$  to  $2^{31} - 1$ .

All values less than zero retrieve the same result.

### FioranoHAKRPCProvider

Presented below are details of the parameters in **Fiorano->HA->HAKRPCProvider->FioranoHAKRPCProvider->config**.

### BackupHAPort

The BackupHAPort parameter specifies the port of the backup peer Server on which the peer is listens for status requests sent by the Server.

#### Valid values:

The default value of the BackupHAPort parameter is **3000**.

**Note:** It is mandatory to have the BackupHAPort parameter to run HA.

### BackupHAIPAddress

The BackupHAIPAddress parameter specifies the IP address of the backup peer Server on which the peer listens for status requests sent by the Server.

#### Valid values:

The default value of the BackupHAIPAddress parameter is **localhost**.

**Note:** It is mandatory to have the BackupHAIPAddress parameter to run HA.

### SocketTimeout

The SocketTimeout parameter indicates the time in milliseconds before the socket created for communication with the peer Server timesout occurs.

---

**Valid values:**

The default value for the SocketTimeOut parameter is **30000**.

The range of integer values considered valid by the SocketTimeout are  $-2^{31}$  to  $2^{31} - 1$

All values less than zero retrieve the same result.

**SocketCreationTimeout**

The SocketCreationTimeout indicates the time in milliseconds within which socket must connect with the peer Server failing which the socket creation attempt fails.

**Valid values:**

The default value for the SocketCreationTimeout is **30000**.

The range of integer values considered valid by the SocketCreationTimeout are  $-2^{31}$  to  $2^{31} - 1$ .

All values less than zero retrieve the same result.

**HaStateNotifBroadcaster**

Presented below are the details of the parameters in **Fiorano->HA->HManager->EventManager->HaStateNotifBroadcaster**.

**LoggerName**

The LoggerName parameter provides a unique Logger Name.

**Valid values:**

The default value of the LoggerName parameter is **null**.

Any String may be used as a valid value for this parameter.

**FioranoStatusPersister**

Presented below are the details of the parameters in **Fiorano->HA->HManager->StatusPersister->FioranoStatusPersister->config**.

**Path**

In Replication based HA mode state information is replicated between FioranoMQ Servers through replication channels. Loading and storing of the replicated is done by the **StatusPersister**. The Path parameter helps configure the path of file where the status that is persisted is located.

---



**Valid values:**

The default value of the Path parameter is **haStatus.dat**.

Any valid file name may be used by this parameter.

Given a relative path for a zip file name, the zip file is created relative that path in the directory: **<current-profile>/run/**. If its an absolute path for a file name is given, the zip file is created in that directory.

## FioranoHAManager

Presented below are the details of the parameters in **Fiorano->HA->HAManager->RpManager->FioranoHAManager->config**.

### Primary

The Primary parameter is a boolean parameter that indicates whether the acting Server acts as the primary HA Server when in the Replication HA mode. In FioranoMQ's HA implementation, one of the two HA Servers is the primary server while the other is the secondary Server. For more information about FioranoMQ's HA implementation, please refer to *FioranoMQ Concepts Guide Chapter 16* or *FioranoMQ High Availability Guide*.

**Valid values:**

The default value of the Primary parameter is **yes**.

- yes - Indicates that the Server is the primary server.
- no - Indicates that the Server is the secondary server.

## GatewayListenerNotUpMesg

In FioranoMQ's HA implementation a gateway machine is used to detect the HA Server that is no longer available on the network. It becomes imperative to choose a gateway machine that is least expected to be out of the network. It makes sense to use the actual gateway Server of the network where the enterprise Server is deployed as the Gateway machine for HA.

The GatewayListenerNotUpMesg parameter helps identify the message that will be displayed when the acting Server finds that no listener is present on the port configured.

**Valid values:**

The default value for the GatewayListenerNotUpMesg parameter is **Connection refused**.

Any String may be used as a valid value for this parameter.

---

## PingInterval

The acting HA Server pings its peer Server intermittently to exchange status information. PingInterval is the time interval in milliseconds after which the remote Server is pinged in Replication HA mode.

### Valid values:

The default value for the PingInterval parameter is **30000**.

The range of integer values considered valid by the PingInterval are  $-2^{31}$  to  $2^{31} - 1$ . All values less than zero retrieve the same result.

## GatewayServerPort

In FioranoMQ's HA implementation a gateway machine is used to detect the HA Server that is no longer available on the network. It becomes imperative to choose a gateway machine that is least expected to be out of the network. It makes sense to use the actual gateway Server of the network where the enterprise Server is deployed as the Gateway machine for HA.

The GatewayServerPort parameter helps specify the port on which the Gateway machine listens for incoming requests.

### Valid values:

The default value GatewayServerPort parameter is **7**.

The range of integer values considered valid by the GatewayServerPort are  $-2^{31}$  to  $2^{31} - 1$ .

**Note:** The port should not be in use..

## SocketCreationTimeout

SocketCreationTimeout is the time in milliseconds within which the socket has to connect with the peer Server failing which the socket creation attempt fails.

### Valid values:

The default value for the SocketCreationTimeout is **10000**.

The range of integer values considered valid by the SocketCreationTimeout are  $-2^{31}$  to  $2^{31} - 1$ . All values less than zero retrieve the same result.

## ServerName

The ServerName parameter specifies the name of the Server running in the Replication HA mode.

### Valid values:

The default value for the ServerName is **FMQServer**

---

Any String may be used as a valid value for this parameter.

**Example:**

Naming the server in the most relevant way that explains its purpose makes distinguishing it from other servers easier.

### GatewayServerIPAddress

In FioranoMQ's HA implementation a gateway machine is used to detect the HA Server which is no longer available on the network. It makes sense to use the actual gateway Server of the network in which the enterprise Server is deployed as the Gateway machine for HA.

The GatewayServerIPAddress parameter helps specify the IP address on which the Gateway machine listens for incoming requests.

**Valid values:**

The default value for the GatewayServerIPAddress parameter is **localhost**.

**Example:**

Choose a machine that is least expected to be out of the network to ensure that it is most likely to perform its function as a Gateway machine.

### MaxWaitTimeout

When an acting Server notices that there has been a change in its peer Server state it must change its state appropriately. While the acting Server begins changing its state it starts a timer. If for some reason the state change is not completed after a reasonable amount of time the acting server must be altered.

The MaxWaitTimeout parameter specifies the maximum waiting timeout in milliseconds the local Server waits for a state transition to complete.

**Valid values:**

The default value for the MaxWaitTimeout parameter is **30000**.

The range of integer values considered valid by the MaxWaitTimeout are  $-2^{31}$  to  $2^{31} - 1$

All values less than zero retrieve the same result.

### WaitTimeForBackupServer

This parameter indicates the wait time to detect backup server during local server bootup. If backup server is not available then local server will switch to standalone after acquiring lock. A higher value of this parameter can avoid one of the server switching to standalone, thus avoiding unnecessary database replication at the cost of more wait time during server boot up.

---

**Default value:**

30000(units in milliseconds)

**Legal values:**

Any positive integer which represents a few seconds.

### MaxPingCount

This parameter indicates the maximum number of times gateway server will be pinged for detecting a server failure. This will be useful in case of a weak network link between gateway server and ha server. Increasing this parameter should be done after consulting Fiorano support team as increasing this parameter can disrupt ha functionality.

**Default value:** 1

### FioranoFMQKernel

Presented below are the details for the parameters in **Fiorano->HA->FMQKernel->FioranoFMQKernel->config**.

### MQUnDeploymentLists

While in the Active mode the HA Server works normally. While in the Passive mode, the HA Server only monitors its peer and does not handle any client requests. All client connections to the Server when it is in the Passive mode are refused. If a peer Server goes dead the acting Server goes into the Standalone state. In order to **not accept any client connections** while in the Passive state, a few components of the Server need to be undeployed.

These components are listed in FioranoMQ specified files. The MQUnDeploymentLists parameter helps specify lists of files (separated by commas) containing Fiorano specific components that are to be undeployed when necessary.

**Valid values:**

The default value for the MQUnDeploymentLists parameter is **kernel.lst,DefaultMQObjects.lst**.

A comma separated list of .lst files is a valid value for this parameter.

Given a relative path for a file name the files are searched for in the directory: <current-profile>/deploy/. If an absolute path is given files are searched in that directory.

---

## ExternalUnDeploymentLists

When in the Active mode the HA Server works normally. While in the Passive mode, the HA Server only monitors its peer and does not handle any client requests. All client connection to the Server when it is in the Passive mode are refused. If a peer Server goes dead the Server goes into the Standalone state. In order to **not accept any client connections** while in passive state, a few components of the Server need to be undeployed. When the Server is in the Active state these components need to be undeployed.

The components that need to be undeployed are listed in FioranoMQ specified files. The ExternalUnDeploymentLists parameter helps specify lists of files (separated by commas) containing external components that are to be undeployed when necessary.

### Valid values:

The default value for the ExternalUnDeploymentLists parameter is null.

A comma separated list of .lst files is a valid value for this parameter.

Given a relative path for a file name the files are searched for in the directory: <current-profile>/deploy/. If an absolute path is given files are searched in the directory.

## MQDeploymentLists

When in the Active mode the HA Server works normally. While in the Passive mode, the HA Server only monitors its peer and does not handle any client requests. All client connections to the Server when it is in the Passive mode are refused. If a peer Server goes dead then the acting Server goes into the Standalone state. In order to **not accept any client connections** while in passive state, a few components of the Server need to be undeployed. These components are redeployed when the Server starts accepting connections.

The components that need to be redeployed are listed in FioranoMQ specified files. The MQDeploymentLists parameter helps specify lists of files (separated by commas) containing Fiorano specific components that are to be redeployed when necessary.

### Valid values

The default value MQDeploymentLists parameter is **kernel.lst,DefaultMQObjects.lst**

A comma separated list of .lst files is a valid value for this parameter.

Given a relative path for a file name the files are searched for in the directory: <current-profile>/deploy/. If an absolute path is given files are searched in that directory.

---

## ExternalDeploymentLists

When in the Active mode the HA Server works normally. While in the Passive mode, the HA Server only monitors its peer and does not handle any client requests. All client connections to the Server when it is in the Passive mode are refused. In case a peer Server goes dead the acting Server goes into the Standalone state. In order to **not accept any client connections** while in the Passive state, a few components of the Server need to be undeployed. There may be external components that need to be redeployed when the Server goes back to the Active state.

The components to be undeployed are listed in Fiorano files. The ExternalDeploymentLists parameter helps specify lists of files (separated by commas) containing external components that are to be redeployed when necessary.

### Valid values:

The default value for the ExternalDeploymentLists parameter is null.

A comma separated list of .lst files is a valid value for this parameter.

Given a relative path for a file name the files are searched for in the directory: <current-profile>/deploy/. If an absolute path is given files are searched in the directory.

## FioranoRpTopicManager

Presented below are the details for the parameters in **Fiorano->HA->ReplicableTopicMgr->RpTopicManager->FioranoRpTopicManager->config**.

### ZipPath

In the Replicable mode of the FioranoMQ HA Server, consistency between the individual HA Servers must be maintained at all times. To be able to synchronize all topic related information a zip file containing topic related information present in the Server is created. The ZipPath parameter allows the configuration of the path in which that file is located.

### Valid values:

The default value for the ZipPath parameter is **fmq\_tgmsdb.zip**.

Any valid filename for a zip file may be used for this parameter.

Given a relative path for a zip file name, the zip file is created relative that path in the directory: <current-profile>/run/. If its an absolute path for a file name is given, the zip file is created in that directory.

### UnzipDir

In the Replicable mode of the FioranoMQ HA Server, consistency between the individual HA Servers must be maintained at all times. To be able to synchronize topic related information, a zip file containing topic related information is created. The UnZipDir parameter allows the configuration of the path in which that zip file is temporarily unzipped.

---

### Valid values

The default value of the UnZipDir parameter is **TGMS\_TEMP**.

Any valid filename may be used for this parameter.

Given a relative path for a zip file name, the zip file is created relative that path in the directory: **<current-profile>/run/**. If its an absolute path for a file name is given, the zip file is created in that directory.

### SocketTimeout

The SocketTimeout parameter indicates the time in milliseconds before the socket times out for the replicable component occurs. Replication of all topic related information must be done within this time.

### Valid values:

The default value for the SocketTimeout parameter is **240000** (equal to four minutes).

The range of integer values considered valid by the SocketTimeout are  $-2^{31}$  to  $2^{31} - 1$ . All values less than zero retrieve the same result.

### FioranoRpQueueManager

Presented below are the details for the parameters in **Fiorano->HA->ReplicableQueueMgr->RpQueueManager->FioranoRpQueueManager->config**.

### ZipPath

In the Replicable mode of the FioranoMQ HA Server, consistency between the individual HA Servers must be maintained at all times. To be able to synchronize all the queue related information a zip file containing queue related information present in the Server is created. The ZipPath parameter allows the configuration of the path in which that file is located.

### Valid values:

The default value for the ZipPath parameter is **fmq\_qgmsdb.zip**.

Any valid filename for a zip file may be used as a parameter.

Given a relative path for a zip file name, the zip file is created relative that path in the directory: **<current-profile>/run/**. If its an absolute path for a file name is given, the zip file is created in that directory.

---

## UnzipDir

In the Replicable mode of the FioranoMQ HA Server, consistency between the individual HA Servers must be maintained at all times. To be able to synchronize queue related information, a zip file containing queue related information is created. The UnzipDir parameter allows the configuration of the path in which that zip file is temporarily unzipped.

### Valid values

The default value for the UnzipDir parameter is **QGMS\_TEMP**.

Any valid filename may be used as a parameter.

Given a relative path for a zip file name, the zip file is created relative that path in the directory: <current-profile>/run/. If its an absolute path for a file name is given, the zip file is created in that directory.

## SocketTimeout

The SocketTimeout indicates the time in milliseconds before the socket timesout for the replicable component occurs. Replication of all queue related information must be done within this time.

### Valid values

The default value for the SocketTimeout parameter is **240000** (equal to four minutes).

The range of integer values considered valid by the SocketCreationTimeout are  $-2^{31}$  to  $2^{31}-1$

All values less than zero retrieve the same result.

## Secondary Server Configuration

### FioranoHAConnectionManager

Presented below are the details of the parameters in **Fiorano->HA->HAConnectionManager->FioranoHAConnectionManager->config**.

## Port

The Port specifies the port on which HA Manager listens for connections from the peer HA Server. In addition the HA Server listens for a connection from its HA peer Server to determine the status of its peer on this port. The Port parameter is used specifies this port.

### Valid values

The default value for the Port parameter is **3000**.

---



The range of integer values considered valid by the SocketCreationTimeout are  $-2^{31}$  to  $2^{31}-1$

**Note:** The port specified should not be in use..

### NagleAlgo

The NagleAlgo is a boolean parameter that determines whether Nagle's Algorithm, is enabled at the time of socket creation with the peer HA Server. Nagle's algorithm is used in TCP/IP networks for congestion control. It works by coalescing a number of small outgoing messages and sending them all together. If there is a sent packet for which the sender has received no acknowledgment, the sender output needs to be buffered until it there is a full packet worth of output which can then be sent in one go.

#### Valid values:

The default value for the NagleAlgo is **no**.

- **yes** – Indicates that the NagleAlgo is enabled.
- **no** – Indicates that NagleAlgo is not enabled.

#### Example:

The Nagle algorithm should not be enabled in situations involving **Delayed ACK** as that will result in TCP performance problems.

### SocketInitializationTimeout

The SocketInitializationTimeout parameter indicates the time in milliseconds within which a client socket should identify itself and exchange its version number with the Server. The version number exchange is an authentication mechanism employed by FioranoMQ.

#### Valid values:

The default value of the SocketInitializationTimeout is **60000** (equal to one minute).

The range of integer values considered valid by the SocketInitializationTimeout are  $-2^{31}$  to  $2^{31}-1$

All values less than zero retrieve the same result.

### SyncTopicStubManager

Presented below are the details for the parameters in **Fiorano->HA->HAConnectionManager->HAServiceManager->HSubSystems->SyncTopicStubManager**.

---

## MinServiceID

FioranoMQ generates a serviceID with each request associated within a subsystem. The range of serviceIDs that are associated with a subsystem define the operations that are accessible to that subsystem. The MinServiceID value defines the minimum value of that range.

### Valid values:

The default value for the MinServiceID is null. A null value indicates that there is no defined range of serviceIDs.

The range of integer values considered valid by the MinServiceID are  $-2^{31}$  to  $2^{31} - 1$

All values less than zero retrieve the same result.

## MaxServiceID

FioranoMQ generates a serviceID with each request associated within a subsystem. The range of serviceIDs that are associated with a subsystem define the operations that are accessible to that subsystem. The MaxServiceID value defines the minimum value of that range.

### Valid values:

The default value for the MaxServiceID is null. A null value indicates that there is no defined range of serviceIDs. The range of integer values considered valid by the MaxServiceID are  $-2^{31}$  to  $2^{31} - 1$ . All values less than zero retrieve the same result.

## RealmStubManager

Presented below are the details for the parameters in **Fiorano->HA->HAConnectionManager->HAServiceManager->HSubSystems->RealmStubManager**.

### MinServiceID

FioranoMQ generates a serviceID with each request associated within a subsystem. The range of serviceIDs that are associated with a subsystem define the operations that are accessible to that subsystem. The MinServiceID value defines the minimum value of that range.

### Valid values:

The default value for the MinServiceID is null. A null value indicates that there is no defined range of serviceIDs. The range of integer values considered valid by the MinServiceID are  $-2^{31}$  to  $2^{31} - 1$ . All values less than zero retrieve the same result.

## MaxServiceID

FioranoMQ generates a serviceID with each request associated within a subsystem. The range of serviceIDs that are associated with a subsystem define the operations that are accessible to that subsystem. The MaxServiceID value defines the minimum value of that range.

---

### **Valid values:**

The default value for the MaxServiceID is null. A null value indicates that there is no defined range of serviceIDs. The range of integer values considered valid by the MaxServiceID are -  $2^{31}$  to  $2^{31} - 1$ . All values less than zero retrieve the same result.

## **QGMSSubManager**

Presented below are the details for the parameters present in **Fiorano->HA->HAConnectionManager->HServiceManager->HSubSystems->QGMSSubManager**.

### **MinServiceID**

FioranoMQ generates a serviceID with each request associated within a subsystem. The range of serviceIDs that are associated with a subsystem define the operations that are accessible to that subsystem. The MinServiceID value defines the minimum value of that range.

### **Valid values:**

The default value for the MinServiceID is null. A null value indicates that there is no defined range of serviceIDs. The range of integer values considered valid by the MinServiceID are -  $2^{31}$  to  $2^{31} - 1$ . All values less than zero retrieve the same result.

### **MaxServiceID**

FioranoMQ generates a serviceID with each request associated within a subsystem. The range of serviceIDs that are associated with a subsystem define the operations that are accessible to that subsystem. The MaxServiceID value defines the minimum value of that range.

### **Valid values:**

The default value for the MaxServiceID is null. A null value indicates that there is no defined range of serviceIDs. The range of integer values considered valid by the MaxServiceID are -  $2^{31}$  to  $2^{31} - 1$ . All values less than zero are retrieve the same result.

## **TGMSSubManager**

Presented below are the details for the parameters present in **Fiorano->HA->HAConnectionManager->HServiceManager->HSubSystems->TGMSSubManager**.

### **MinServiceID**

FioranoMQ generates a serviceID with each request associated within a subsystem. The range of serviceIDs that are associated with a subsystem define the operations that are accessible to that subsystem. The MinServiceID value defines the minimum value of that range.

---

**Valid values:**

The default value for the MinServiceID is null. A null value indicates that there is no defined range of serviceIDs. The range of integer values considered valid by the MinServiceID are -  $2^{31}$  to  $2^{31} - 1$ . All values less than zero retrieve the same result.

**MaxServiceID**

FioranoMQ generates a serviceID with each request associated within a subsystem. The range of serviceIDs that are associated with a subsystem define the operations that are accessible to that subsystem. The MaxServiceID value defines the minimum value of that range.

**Valid values:**

The default value for the MaxServiceID is null. A null value indicates that there is no defined range of serviceIDs.

The range of integer values considered valid by the MaxServiceID are -  $2^{31}$  to  $2^{31} - 1$ . All values less than zero retrieve the same result.

**SyncRealmStubManager**

Presented below are the details for the parameters present in **Fiorano->HA->HAConnectionManager->HAServiceManager->HSubSystems->SyncRealmStubManager**.

**MinServiceID**

FioranoMQ generates a serviceID with each request associated within a subsystem. The range of serviceIDs that are associated with a subsystem define the operations that are accessible to that subsystem. The MinServiceID value defines the minimum value of that range.

**Valid values:**

The default value for the MinServiceID is null. A null value indicates that there is no defined range of serviceIDs. The range of integer values considered valid by the MinServiceID are -  $2^{31}$  to  $2^{31} - 1$ . All values less than zero retrieve the same result.

**MaxServiceID**

FioranoMQ generates a serviceID with each request associated within a subsystem. The range of serviceIDs that are associated with a subsystem define the operations that are accessible to that subsystem. The MaxServiceID value defines the minimum value of that range.

**Valid values:**

The default value for the MaxServiceID is null. A null value indicates that there is no defined range of serviceIDs. The range of integer values considered valid by the MaxServiceID are -  $2^{31}$  to  $2^{31} - 1$ . All values less than zero retrieve the same result.

---

## SyncNamingStubManager

Presented below are the details for the parameters present in **Fiorano->HA->HAConnectionManager->HServiceManager->HSubSystems->SyncNamingStubManager**.

### MinServiceID

FioranoMQ generates a serviceID with each request associated within a subsystem. The range of serviceIDs that are associated with a subsystem define the operations that are accessible to that subsystem. The MinServiceID value defines the minimum value of that range.

#### Valid values:

The default value for the MinServiceID is null. A null value indicates that there is no defined range of serviceIDs. The range of integer values considered valid by the MinServiceID are -  $2^{31}$  to  $2^{31} - 1$ . All values less than zero retrieve the same result.

### MaxServiceID

FioranoMQ generates a serviceID with each request associated within a subsystem. The range of serviceIDs that are associated with a subsystem define the operations that are accessible to that subsystem. The MaxServiceID value defines the minimum value of that range.

#### Valid values:

The default value for the MaxServiceID is null. A null value indicates that there is no defined range of serviceIDs. The range of integer values considered valid by the MaxServiceID are -  $2^{31}$  to  $2^{31} - 1$ . All values less than zero retrieve the same result.

## NamingStubManager

Presented below are the details for the parameters present in **Fiorano->HA->HAConnectionManager->HServiceManager->HSubSystems->NamingStubManager**.

### MinServiceID

FioranoMQ generates a serviceID with each request associated within a subsystem. The range of serviceIDs that are associated with a subsystem define the operations that are accessible to that subsystem. The MinServiceID value defines the minimum value of that range.

#### Valid values

The default value for the MinServiceID is null. A null value indicates that there is no defined range of serviceIDs.

The range of integer values considered valid by the MinServiceID are -  $2^{31}$  to  $2^{31} - 1$

All values less than zero retrieve the same result.

---

## MaxServiceID

FioranoMQ generates a serviceID with each request associated within a subsystem. The range of serviceIDs that are associated with a subsystem define the operations that are accessible to that subsystem. The MaxServiceID value defines the minimum value of that range.

### Valid values:

The default value for the MaxServiceID is null. A null value indicates that there is no defined range of serviceIDs. The range of integer values considered valid by the MaxServiceID are -  $2^{31}$  to  $2^{31} - 1$ . All values less than zero retrieve the same result.

## SyncQueueStubManager

Presented below are the details for the parameters present in **Fiorano->HA->HAConnectionManager->HServiceManager->HSubSystems->SyncQueueStubManager**.

## MinServiceID

FioranoMQ generates a serviceID with each request associated within a subsystem. The range of serviceIDs that are associated with a subsystem define the operations that are accessible to that subsystem. The MinServiceID value defines the minimum value of that range.

### Valid values

The default value for the MinServiceID is null. A null value indicates that there is no defined range of serviceIDs. The range of integer values considered valid by the MinServiceID are -  $2^{31}$  to  $2^{31} - 1$ . All values less than zero retrieve the same result.

## MaxServiceID

FioranoMQ generates a serviceID with each request associated within a subsystem. The range of serviceIDs that are associated with a subsystem define the operations that are accessible to that subsystem. The MaxServiceID value defines the minimum value of that range.

### Valid values:

The default value for the MaxServiceID is null. A null value indicates that there is no defined range of serviceIDs. The range of integer values considered valid by the MaxServiceID are -  $2^{31}$  to  $2^{31} - 1$ . All values less than zero retrieve the same result.

## RpStateStubManager

Presented below are the details for the parameters present in **Fiorano->HA->HAConnectionManager->HServiceManager->HSubSystems->RpStateStubManager**.

---

## MinServiceID

FioranoMQ generates a serviceID with each request associated within a subsystem. The range of serviceIDs that are associated with a subsystem define the operations that are accessible to that subsystem. The MinServiceID value defines the minimum value of that range.

### Valid values:

The default value for the MinServiceID is 2001.

The range of integer values considered valid by the MinServiceID are  $-2^{31}$  to  $2^{31} - 1$ . All values less than zero retrieve the same result.

## MaxServiceID

FioranoMQ generates a serviceID with each request associated within a subsystem. The range of serviceIDs that are associated with a subsystem define the operations that are accessible to that subsystem. The MaxServiceID value defines the minimum value of that range.

### Valid values:

The default value for the MinServiceID is 3000.

The range of integer values considered valid by the MaxServiceID are  $-2^{31}$  to  $2^{31} - 1$ . All values less than zero retrieve the same result.

## FioranoRpRealmManager

Presented below are the details for the parameters in **Fiorano->HA->ReplicableRealmMgr->RpRealmManager->FioranoRpRealmManager->config**.

## AclZipPath

In the Replicable mode of the FioranoMQ HA Server, consistency between the individual HA Servers must be maintained at all times. In order to be able to synchronize realm related (ACL based) information a zip file containing the ACL information present in this server must be created. The AclZipPath parameter allows the configuration of the path where this file is located.

### Valid values:

The default value of the AclZipPath is **fmq\_acl.zip**.

Any valid filename for a zip file may be used for this parameter.

Given a relative path for a zip file name, the zip file is created relative that path in the directory: **<current-profile>/run/**. If its an absolute path for a file name is given, the zip file is created in that directory.

---

## AclUnzipDir

In the Replicable mode of the FioranoMQ HA Server, consistency between the individual HA Servers must be maintained at all times. In order to be able to synchronize realm related (ACL based) information a zip file is created using the ACL information. The AclUnzipDir parameter allows the configuration of the path where the zip file is temporarily unzipped.

### Valid values:

The default value of the AclUnzipDir parameter is **ACL\_TEMP**.

Any valid filename may be used for this parameter.

Given a relative path for a zip file name, the zip file is created relative that path in the directory: <current-profile>/run/. If its an absolute path for a file name is given, the zip file is created in that directory.

## PrincipalZipPath

In the Replicable mode of the FioranoMQ HA Server, consistency between the individual HA Servers must be maintained at all times. In order to be able to synchronize principal related (User based) information a zip file is created using the information related to the principal present in the Server. The PrincipalZipPath parameter allows the configuration of the path in where this file is located.

### Valid values:

The default value of the PrincipalZipPath parameter is **fmq\_principal.zip**.

Any valid filename for a zip file may be used for this parameter.

Given a relative path for a zip file name, the zip file is created relative that path in the directory: <current-profile>/run/. If its an absolute path for a file name is given, the zip file is created in that directory.

## PrincipalUnzipDir

In the Replicable mode of the FioranoMQ HA Server, consistency between the individual HA Servers must be maintained at all times. In order to be able to synchronize principal related (User based) information a zip file is created using the information related to the principal. The PrincipalUnzipDir parameter allows the configuration of the path where this zip file is temporarily unzipped.

### Valid values:

The default value of the PrincipalUnzipDir parameter is **PRINCIPAL\_TEMP**.

Any valid filename may be used for this parameter.

Given a relative path for a zip file name, the zip file is created relative that path in the directory: <current-profile>/run/. If its an absolute path for a file name is given, the zip file is created in that directory.

---



## SocketTimeout

The SocketTimeout parameter indicates the time in milliseconds before the socket times out for this replicable component occurs. Replication of the principal and realm related information must be done within this time.

### Valid values:

The default value of the SocketTimeout parameter is **240000** (equal to four minutes).

The range of integer values considered valid by the SocketTimeout parameter are  $-2^{31}$  to  $2^{31} - 1$

All values less than zero retrieve the same result.

## FioranoRpNamingManager

Presented below are the details for the parameters in **Fiorano->HA->ReplicableNamingMgr->RpNamingManager->FioranoRpNamingManager->config**.

## ZipPath

In the Replicable mode of the FioranoMQ HA Server, consistency between the individual HA Servers must be maintained at all times. In order to be able to synchronize name related information a zip file using naming related information present in the Server is created. The ZipPath parameter allows the configuration of the path where this file is located.

### Valid values:

The default value of the ZipPath parameter is **fmq\_nmdb.zip**.

Any valid file name for a zip file may be used for this parameter.

Given a relative path for a zip file name, the zip file is created relative that path in the directory: <current-profile>/run/. If its an absolute path for a file name is given, the zip file is created in that directory.

## UnzipDir

In the Replicable mode of the FioranoMQ HA Server, consistency between the individual HA Servers must be maintained at all times. In order to be able to synchronize name related information, a zip file using naming related information is created. The UnzipDir parameter allows the configuration of the path where the zip file is temporarily unzipped.

### Valid values:

The default value for the UnzipDir parameter is **NM\_TEMP**.

Any valid filename may be used for this parameter.

---

Given a relative path for a zip file name, the zip file is created relative that path in the directory: <current-profile>/run/. If its an absolute path for a file name is given, the zip file is created in that directory.

### SocketTimeout

The SocketTimeout parameter indicates the time in milliseconds before the socket times out for this replicable component occurs. Replication of the principal and realm related information must be done within this time.

#### Valid values:

The default value of the SocketTimeout parameter is **240000** (equal to four minutes).

The range of integer values considered valid by the SocketTimeout parameter are  $-2^{31}$  to  $2^{31} - 1$

All values less than zero retrieve the same result.

### FioranoHAKRPCProvider

Presented below are the details for the parameters in **Fiorano->HA->HAKRPCProvider->FioranoHAKRPCProvider->config**.

### BackupHAPort

The BackupHAPort parameter specifies the port of the backup peer Server on which the peer is listens for status requests sent by the Server.

#### Valid values:

The default value of the BackupHAPort parameter is **2000**.

**Note:** It is mandatory to have the BackupHAPort parameter to run HA.

### BackupHAIPAddress

The BackupHAIPAddress parameter specifies the IP address of the backup peer Server on which the peer listens for status requests sent by the Server.

#### Valid values:

The default value of the BackupHAIPAddress parameter is **localhost**.

**Note:** It is mandatory to have the BackupHAIPAddress parameter to run HA.

---

## SocketTimeout

The SocketTimeout parameter indicates the time in milliseconds before the socket created for communication with the peer Server times out occurs.

### Valid values:

The default value for the SocketTimeout parameter is **30000**.

The range of integer values considered valid by the SocketTimeout are  $-2^{31}$  to  $2^{31} - 1$

All values less than zero retrieve the same result.

## SocketCreationTimeout

The SocketCreationTimeout indicates the time in milliseconds within which socket must connect with the peer Server failing which the socket creation attempt fails.

### Valid values:

The default value for the SocketCreationTimeout is **30000**.

The range of integer values considered valid by the SocketCreationTimeout are  $-2^{31}$  to  $2^{31} - 1$ .

All values less than zero retrieve the same result.

## HaStateNotifBroadcaster

Presented below are the details for the parameters in **Fiorano->HA->HAManager->EventManager->HaStateNotifBroadcaster**.

## LoggerName

The LoggerName parameter provides a unique Logger Name.

### Valid values:

The default value of the LoggerName parameter is **null**.

Any String may be used as a valid value for this parameter.

## FioranoStatusPersister

Presented below are the details for the parameters in **Fiorano->HA->HAManager->StatusPersister->FioranoStatusPersister->config**.

---

## Path

In Replication based HA mode state information is replicated between FioranoMQ Servers through replication channels. Loading and storing of the replicated is done by the **StatusPersister**. The Path parameter helps configure the path of file where the status that is persisted is located.

### Valid values:

The default value of the Path parameter is **haStatus.dat**.

Any valid file name may be used by this parameter.

Given a relative path for a zip file name, the zip file is created relative that path in the directory: <current-profile>/run/. If its an absolute path for a file name is given, the zip file is created in that directory.

## FioranoHAManager

Presented below are the details for the parameters in **Fiorano->HA->HAManager->RpManager->FioranoHAManager->config**.

## Primary

The Primary parameter is a boolean parameter that indicates whether the acting Server acts as the primary HA Server when in the Replication HA mode. In FioranoMQ's HA implementation, one of the two HA Servers is the primary server while the other is the secondary Server. For more information about FioranoMQ's HA implementation, please refer to *FioranoMQ Concepts Guide Chapter 16* or *FioranoMQ High Availability Guide*.

### Valid values:

The default value of the Primary parameter is **no**.

- **yes** - Indicates that the Server is the primary server.
- **no** - Indicates that the Server is the secondary server.

## GatewayListenerNotUpMesg

In FioranoMQ's HA implementation a gateway machine is used to detect the HA Server that is no longer available on the network. It becomes imperative to choose a gateway machine that is least expected to be out of the network. It makes sense to use the actual gateway Server of the network where the enterprise Server is deployed as the Gateway machine for HA.

The GatewayListenerNotUpMesg parameter helps identify the message that will be displayed when the acting Server finds that no listener is present on the port configured.

### Valid values:

The default value for the GatewayListenerNotUpMesg parameter is **Connection refused**.

---

Any String may be used as a valid value for this parameter.

### PingInterval

The acting HA Server pings its peer Server intermittently to exchange status information. PingInterval is the time interval in milliseconds after which the remote Server is pinged in Replication HA mode.

#### Valid values:

The default value for the PingInterval parameter is **30000**.

The range of integer values considered valid by the PingInterval are  $-2^{31}$  to  $2^{31} - 1$ . All values less than zero retrieve the same result.

### GatewayServerPort

In FioranoMQ's HA implementation a gateway machine is used to detect the HA Server that is no longer available on the network. It becomes imperative to choose a gateway machine that is least expected to be out of the network. It makes sense to use the actual gateway Server of the network where the enterprise Server is deployed as the Gateway machine for HA.

The GatewayServerPort parameter helps specify the port on which the Gateway machine listens for incoming requests.

#### Valid values:

The default value GatewayServerPort parameter is **7**.

The range of integer values considered valid by the GatewayServerPort are  $-2^{31}$  to  $2^{31} - 1$ .

**Note:** The port should not be in use..

### SocketCreationTimeout

The SocketCreationTimeout indicates the time in milliseconds within which socket must connect with the peer Server failing which the socket creation attempt fails.

#### Valid values:

The default value for the SocketCreationTimeout is **10000**.

The range of integer values considered valid by the SocketCreationTimeout are  $-2^{31}$  to  $2^{31} - 1$ .

All values less than zero retrieve the same result.

---

## ServerName

The ServerName parameter specifies the name of the Server running in the Replication HA mode.

### Valid values:

The default value for the ServerName is **FMQServer**

Any String may be used as a valid value for this parameter.

### Example:

Naming the server in the most relevant way that explains its purpose makes distinguishing it from other servers easier.

## GatewayServerIPAddress

In FioranoMQ's HA implementation a gateway machine is used to detect the HA Server which is no longer available on the network. It makes sense to use the actual gateway Server of the network in which the enterprise Server is deployed as the Gateway machine for HA.

The GatewayServerIPAddress parameter helps specify the IP address on which the Gateway machine listens for incoming requests.

### Valid values:

The default value for the GatewayServerIPAddress parameter is **localhost**.

### Example:

Choose a machine that is least expected to be out of the network to ensure that it is most likely to perform its function as a Gateway machine.

In FioranoMQ's HA implementation a gateway machine is used to detect the HA Server which is no longer available on the network. It makes sense to use the actual gateway Server of the network in which the enterprise Server is deployed as the Gateway machine for HA.

The GatewayServerIPAddress parameter helps specify the IP address on which the Gateway machine listens for incoming requests.

### Valid values:

The default value for the GatewayServerIPAddress parameter is **localhost**.

### Example:

Choose a machine that is least expected to be out of the network to ensure that it is most likely to perform its function as a Gateway machine.

---

## MaxWaitTimeout

When an acting Server notices that there has been a change in its peer Server state it must change its state appropriately. While the acting Server begins changing its state it starts a timer. If for some reason the state change is not completed after a reasonable amount of time the acting server must be altered.

The MaxWaitTimeout parameter specifies the maximum waiting timeout in milliseconds the local Server waits for a state transition to complete.

### Valid values:

The default value for the MaxWaitTimeout parameter is **30000**.

The range of integer values considered valid by the SocketCreationTimeout are  $-2^{31}$  to  $2^{31}-1$

All values less than zero retrieve the same result.

## FioranoFMQKernel

Presented below are the details for the parameters in **Fiorano->HA->FMQKernel->FioranoFMQKernel->config**.

## MQUnDeploymentLists

While in the Active mode the HA Server works normally. While in the Passive mode, the HA Server only monitors its peer and does not handle any client requests. All client connections to the Server when it is in the Passive mode are refused. If a peer Server goes dead the acting Server goes into the Standalone state. In order to **not accept any client connections** while in the Passive state, a few components of the Server need to be undeployed.

These components are listed in FioranoMQ specified files. The MQUnDeploymentLists parameter helps specify lists of files (separated by commas) containing Fiorano specific components that are to be undeployed when necessary.

### Valid values:

The default value for the MQUnDeploymentLists parameter is **kernel.lst,DefaultMQObjects.lst**.

A comma separated list of .lst files is a valid value for this parameter.

Given a relative path for a file name the files are searched for in the directory: <current-profile>/deploy/. If an absolute path is given files are searched in that directory.

## ExternalUnDeploymentLists

When in the Active mode the HA Server works normally. While in the Passive mode, the HA Server only monitors its peer and does not handle any client requests. All client connection to the Server when it is in the Passive mode are refused. If a peer Server goes dead the Server goes into the Standalone state. In order to **not accept any client connections** while in passive state, a few components of the Server need to be undeployed. When the Server is in the Active state these components need to be undeployed.

The components that need to be undeployed are listed in FioranoMQ specified files. The ExternalUnDeploymentLists parameter helps specify lists of files (separated by commas) containing external components that are to be undeployed when necessary.

### Valid values:

The default value for the ExternalUnDeploymentLists parameter is null.

A comma separated list of .lst files is a valid value for this parameter.

Given a relative path for a file name the files are searched for in the directory: <current-profile>/deploy/. If an absolute path is given files are searched in that directory.

## MQDeploymentLists

When in the Active mode the HA Server works normally. While in the Passive mode, the HA Server only monitors its peer and does not handle any client requests. All client connections to the Server when it is in the Passive mode are refused. If a peer Server goes dead then the acting Server goes into the Standalone state. In order to **not accept any client connections** while in passive state, a few components of the Server need to be undeployed. These components are redeployed when the Server starts accepting connections.

The components that need to be redeployed are listed in FioranoMQ specified files. The MQDeploymentLists parameter helps specify lists of files (separated by commas) containing Fiorano specific components that are to be redeployed when necessary.

### Valid values

The default value MQDeploymentLists parameter is **kernel.lst,DefaultMQObjects.lst**

A comma separated list of .lst files is a valid value for this parameter.

Given a relative path for a file name the files are searched for in the directory: <current-profile>/deploy/. If an absolute path is given files are searched in that directory.

---



## ExternalDeploymentLists

When in the Active mode the HA Server works normally. While in the Passive mode, the HA Server only monitors its peer and does not handle any client requests. All client connections to the Server when it is in the Passive mode are refused. In case a peer Server goes dead the acting Server goes into the Standalone state. In order to **not accept any client connections** while in the Passive state, a few components of the Server need to be undeployed. There may be external components that need to be redeployed when the Server goes back to the Active state.

The components to be undeployed are listed in Fiorano files. The ExternalDeploymentLists parameter helps specify lists of files (separated by commas) containing external components that are to be redeployed when necessary.

### Valid values:

The default value for the ExternalDeploymentLists parameter is null.

A comma separated list of .lst files is a valid value for this parameter.

Given a relative path for a file name the files are searched for in the directory: <current-profile>/deploy/. If an absolute path is given files are searched in the directory.

## FioranoRpTopicManager

Presented below are the details for the parameters in **Fiorano->HA->ReplicableTopicMgr->RpTopicManager->FioranoRpTopicManager->config**.

### ZipPath

In the Replicable mode of the FioranoMQ HA Server, consistency between the individual HA Servers must be maintained at all times. To be able to synchronize all topic related information a zip file containing topic related information present in the Server is created. The ZipPath parameter allows the configuration of the path in which that file is located.

### Valid values:

The default value for the ZipPath parameter is **fmq\_tgmsdb.zip**.

Any valid filename for a zip file may be used for this parameter.

Given a relative path for a zip file name, the zip file is created relative that path in the directory: <current-profile>/run/. If its an absolute path for a file name is given, the zip file is created in the directory.

### UnzipDir

In the Replicable mode of the FioranoMQ HA Server, consistency between the individual HA Servers must be maintained at all times. In order to be able to synchronize name related information, a zip file using naming related information is created. The UnzipDir parameter allows the configuration of the path where the zip file is temporarily unzipped.

---

**Valid values:**

The default value for the UnzipDir parameter is **TGMS\_TEMP**.

Any valid filename may be used for this parameter.

Given a relative path for a zip file name, the zip file is created relative that path in the directory: <current-profile>/run/. If its an absolute path for a file name is given, the zip file is created in that directory.

**SocketTimeout**

The SocketTimeout parameter indicates the time in milliseconds before the socket times out for this replicable component occurs. Replication of the principal and realm related information must be done within this time.

**Valid values:**

The default value of the SocketTimeout parameter is **240000** (equal to four minutes).

The range of integer values considered valid by the SocketTimeout parameter are  $-2^{31}$  to  $2^{31} - 1$

All values less than zero retrieve the same result.

**FioranoRpQueueManager**

Presented below are the details for the parameters in **Fiorano->HA->ReplicableQueueMgr->RpQueueManager->FioranoRpQueueManager->config**.

**ZipPath**

In the Replicable mode of the FioranoMQ HA Server, consistency between the individual HA Servers must be maintained at all times. In order to be able to synchronize name related information a zip file using naming related information present in the Server is created. The ZipPath parameter allows the configuration of the path where this file is located.

**Valid values:**

The default value of the ZipPath parameter is **fmq\_qgmsdb.zip**.

Any valid file name for a zip file may be used for this parameter.

Given a relative path for a zip file name, the zip file is created relative that path in the directory: <current-profile>/run/. If its an absolute path for a file name is given, the zip file is created in that directory.

---

## UnzipDir

In the Replicable mode of the FioranoMQ HA Server, consistency between the individual HA Servers must be maintained at all times. In order to be able to synchronize name related information, a zip file using naming related information is created. The UnzipDir parameter allows the configuration of the path where the zip file is temporarily unzipped.

### Valid values:

The default value for the UnzipDir parameter is **QGMS\_TEMP**.

Any valid filename may be used for this parameter.

Given a relative path for a zip file name, the zip file is created relative that path in the directory: <current-profile>/run/. If its an absolute path for a file name is given, the zip file is created in that directory.

## SocketTimeout

The SocketTimeout parameter indicates the time in milliseconds before the socket times out for this replicable component occurs. Replication of the principal and realm related information must be done within this time.

### Valid values:

The default value of the SocketTimeout parameter is **240000** (equal to four minutes).

The range of integer values considered valid by the SocketTimeout parameter are  $-2^{31}$  to  $2^{31} - 1$

All values less than zero retrieve the same result.

---

# Chapter 12: HA Shared Configuration

---

This chapter explains the parameters that can be configured for FioranoMQ Servers running in Shared High Availability mode. These are the various parameters that are configured under the **FioranoMQ→Fiorano→HA→\*** tree node in Shared HA Profiles in Offline configuration using Studio.

For more information on High Availability, refer to the FioranoMQ High Availability Guide

## Primary Server Configuration

### FioranoHAKRPCProvider

Presented below are the details for the parameters in **Fiorano->HA->HAKRPCProvider->FioranoHAKRPCProvider->config**

#### BackupHAPort

The BackupHAPort parameter specifies the port of the backup peer Server on which the peer is listens for status requests sent by the Server.

##### Valid values:

The default value of the BackupHAPort parameter is **3000**.

**Note:** It is mandatory to have the BackupHAPort parameter to run HA.

#### BackupHAIPAddress

The BackupHAIPAddress parameter specifies the IP address of the backup peer Server on which the peer listens for status requests sent by the Server.

##### Valid values:

The default value of the BackupHAIPAddress parameter is **localhost**.

**Note:** It is mandatory to have the BackupHAIPAddress parameter to run HA.

#### SocketTimeout

The SocketTimeOut parameter indicates the time in milliseconds before the socket created for communication with the peer Server times out occurs.

##### Valid values:

The default value for the SocketTimeOut parameter is **30000**.

---

The range of integer values considered valid by the SocketTimeout are  $-2^{31}$  to  $2^{31} - 1$

All values less than zero retrieve the same result.

### SocketCreationTimeout

The SocketCreationTimeout indicates the time in milliseconds within which socket must connect with the peer Server failing which the socket creation attempt fails.

#### Valid values:

The default value for the SocketCreationTimeout is **30000**.

The range of integer values considered valid by the SocketCreationTimeout are  $-2^{31}$  to  $2^{31} - 1$ .

All values less than zero retrieve the same result.

### FioranoHAConnectionManager

Presented below are the details for the parameters in **Fiorano->HA->HAConnectionManager->FioranoHAConnectionManager->config**

#### Port

The Port parameter specifies the port on which the HA Manager listens on for connections from the peer HA Server. i This parameter listens for a connection from HA Peer Server in order to know the status of its peer.

#### Valid values:

The default value of the Port parameter is **2000**.

The range of integer values considered valid by the Port parameter in java are  $-2^{31}$  to  $2^{31} - 1$ .

**Note:** The port may not be used by other services when being used to listen to Peer servers.

#### NagleAlgo

The NagleAlgo parameter is a boolean value that determines whether Nagle's Algorithm is enabled during socket creation with peer HA Server. Nagle's algorithm is used in TCP/IP networks for congestion control. It works by coalescing a number of small outgoing messages and sending them together, all at once. If there is a **sent packet** for which the sender has received no acknowledgment, the sender should keep buffering its output until it has a full packet worth of output, so as to send the entire output in one go.

#### Valid values:

The default value for the NagleAlgo parameter is **no**.

---

- **yes** – Indicates that the NagleAlgo is enabled.
- **no** – Indicates that the NagleAlgo is not enabled.

#### **Example:**

The Nagle algorithm should not be enabled in situations involving **Delayed ACK** as that will cause TCP performance problems.

### **SocketInitializationTimeout**

The SocketInitializationTimeout parameter indicates the time in milliseconds within which a client socket should identify itself and exchange its version number with the Server. The version number exchange is an authentication mechanism that FioranoMQ employs.

#### **Valid values:**

The default value for the SocketInitializationTimeout parameter is **60000** (which is equal to one minute).

The range of integer values considered valid by the SocketInitializationTimeout parameter in java are  $-2^{31}$  to  $2^{31} - 1$ .

All values less than zero retrieve the same result.

### **FioranoHStateStubManager**

Presented below are the details for the parameters in **Fiorano->HA->HAConnectionManager->HServiceManager->HStateStubManager->FioranoHStateStubManager->config**

### **MinServiceID**

The MinServiceID parameter defines a serviceID in FioranoMQ. Each request is associated with a subsystem. A range of serviceIDs associated with a subsystem determine the operations accessible to the subsystem. The MinServiceID defines the minimum value of the range that exists for the serviceIDs.

#### **Valid values:**

The default value for the MinServiceID parameter is null. If the value is specified as null, there is no range defined for serviceIDs.

The range of integer values considered valid by the MinServiceID parameter in java are  $-2^{31}$  to  $2^{31} - 1$ .

All values less than zero retrieve the same result.

---

## MaxServiceID

The MaxServiceID parameter defines a serviceID in FioranoMQ. Each request is associated with a subsystem. A range of serviceIDs associated with a subsystem determine the operations accessible to the subsystem. The MaxServiceID defines the maximum value of the range that exists for the serviceIDs.

### Valid values:

The default value for the MaxServiceID parameter is null. If the value is specified as null, there is no range defined for serviceIDs.

The range of integer values considered valid by the MaxServiceID parameter in java are  $-2^{31}$  to  $2^{31} - 1$ .

All values less than zero retrieve the same result.

## FioranoHAManager

Presented below are the details for the parameters in **Fiorano->HA->HAManager->FioranoHAManager->config**

### Primary

The Primary parameter is a boolean parameter that indicates whether the acting Server acts as the primary HA Server when in the Replication HA mode. In FioranoMQ's HA implementation, one of the two HA Servers is the primary server while the other is the secondary Server. For more information about FioranoMQ's HA implementation please refer to *FioranoMQ Concepts Guide Chapter 16* or *FioranoMQ High Availability Guide*.

### Valid values:

The default value of the Primary parameter is **yes**.

- **yes** - Indicates that the Server is the primary server.
- **no** - Indicates that the Server is the secondary server.

## GatewayListenerNotUpMesg

In FioranoMQ's HA implementation a gateway machine is used to detect the HA Server that is no longer available on the network. It becomes imperative to choose a gateway machine that is least expected to be out of the network. It makes sense to use the actual gateway Server of the network where the enterprise Server is deployed as the Gateway machine for HA.

The GatewayListenerNotUpMesg parameter helps identify the message that will be displayed when the acting Server finds that no listener is present on the port configured.

### Valid values:

The default value for the GatewayListenerNotUpMesg parameter is **Connection refused**.

---

Any String may be used as a valid value for this parameter.

### GatewayServerPort

In FioranoMQ's HA implementation a gateway machine is used to detect the HA Server that is no longer available on the network. It becomes imperative to choose a gateway machine that is least expected to be out of the network. It makes sense to use the actual gateway Server of the network where the enterprise Server is deployed as the Gateway machine for HA.

The GatewayServerPort parameter helps specify the port on which the Gateway machine listens for incoming requests.

#### Valid values:

The default value GatewayServerPort parameter is **7**.

The range of integer values considered valid by the GatewayServerPort are  $-2^{31}$  to  $2^{31} - 1$ .

**Note:** The port should not be in use..

### PingInterval

The acting HA Server pings its peer Server intermittently to exchange status information. PingInterval is the time interval in milliseconds after which the remote Server is pinged in Replication HA mode.

#### Valid values:

The default value for the PingInterval parameter is **30000**.

The range of integer values considered valid by the PingInterval are  $-2^{31}$  to  $2^{31} - 1$ . All values less than zero retrieve the same result.

### SocketCreationTimeout

The SocketCreationTimeout indicates the time in milliseconds within which socket must connect with the peer Server failing which the socket creation attempt fails.

#### Valid values:

The default value for the SocketCreationTimeout is **10000**.

The range of integer values considered valid by the SocketCreationTimeout are  $-2^{31}$  to  $2^{31} - 1$ .

All values less than zero retrieve the same result.

---



## ServerName

The ServerName parameter specifies the name of the Server running in the Replication HA mode.

### Valid values:

The default value for the ServerName is **FMQServer**

Any String may be used as a valid value for this parameter.

### Example:

Naming the server in the most relevant way that explains its purpose makes distinguishing it from other servers easier.

## GatewayServerIPAddress

In FioranoMQ's HA implementation a gateway machine is used to detect the HA Server which is no longer available on the network. It makes sense to use the actual gateway Server of the network in which the enterprise Server is deployed as the Gateway machine for HA.

The GatewayServerIPAddress parameter helps specify the IP address on which the Gateway machine listens for incoming requests.

### Valid values:

The default value for the GatewayServerIPAddress parameter is **localhost**.

### Example:

Choose a machine that is least expected to be out of the network to ensure that it is most likely to perform its function as a Gateway machine.

## FioranoFMQKernel

Presented below are the details for the parameters in **Fiorano->HA->FMQKernel->FioranoFMQKernel->config**

## MQUnDeploymentLists

While in the Active mode the HA Server works normally. While in the Passive mode, the HA Server only monitors its peer and does not handle any client requests. All client connections to the Server when it is in the Passive mode are refused. If a peer Server goes dead the acting Server goes into the Standalone state. In order to **not accept any client connections** while in the Passive state, a few components of the Server need to be undeployed.

These components are listed in FioranoMQ specified files. The MQUnDeploymentLists parameter helps specify lists of files (separated by commas) containing Fiorano specific components that are to be undeployed when necessary.

---

### Valid values:

The default value for the MQUnDeploymentLists parameter is **kernel.lst,DefaultMQObjects.lst**.

A comma separated list of .lst files is a valid value for this parameter.

Given a relative path for a file name the files are searched for in the directory: <current-profile>/deploy/. If an absolute path is given files are searched in that directory.

### ExternalUnDeploymentLists

When in the Active mode the HA Server works normally. While in the Passive mode, the HA Server only monitors its peer and does not handle any client requests. All client connection to the Server when it is in the Passive mode are refused. If a peer Server goes dead the Server goes into the Standalone state. In order to **not accept any client connections** while in passive state, a few components of the Server need to be undeployed. When the Server is in the Active state these components need to be undeployed.

The components that need to be undeployed are listed in FioranoMQ specified files. The ExternalUnDeploymentLists parameter helps specify lists of files (separated by commas) containing external components that are to be undeployed when necessary.

### Valid values:

The default value for the ExternalUnDeploymentLists parameter is null.

A comma separated list of .lst files is a valid value for this parameter.

Given a relative path for a file name the files are searched for in the directory: <current-profile>/deploy/. If an absolute path is given files are searched in the directory.

### MQDeploymentLists

When in the Active mode the HA Server works normally. While in the Passive mode, the HA Server only monitors its peer and does not handle any client requests. All client connections to the Server when it is in the Passive mode are refused. If a peer Server goes dead then the acting Server goes into the Standalone state. In order to **not accept any client connections** while in passive state, a few components of the Server need to be undeployed. These components are redeployed when the Server starts accepting connections.

The components that need to be redeployed are listed in FioranoMQ specified files. The MQDeploymentLists parameter helps specify lists of files (separated by commas) containing Fiorano specific components that are to be redeployed when necessary.

### Valid values

The default value MQDeploymentLists parameter is **kernel.lst,DefaultMQObjects.lst**

A comma separated list of .lst files is a valid value for this parameter.

---

Given a relative path for a file name the files are searched for in the directory: <current-profile>/deploy/. If an absolute path is given files are searched in that directory.

## ExternalDeploymentLists

When in the Active mode the HA Server works normally. While in the Passive mode, the HA Server only monitors its peer and does not handle any client requests. All client connections to the Server when it is in the Passive mode are refused. In case a peer Server goes dead the acting Server goes into the Standalone state. In order to **not accept any client connections** while in the Passive state, a few components of the Server need to be undeployed. There may be external components that need to be redeployed when the Server goes back to the Active state.

The components to be undeployed are listed in Fiorano files. The ExternalDeploymentLists parameter helps specify lists of files (separated by commas) containing external components that are to be redeployed when necessary.

### Valid values:

The default value for the ExternalDeploymentLists parameter is null.

A comma separated list of .lst files is a valid value for this parameter.

Given a relative path for a file name the files are searched for in the directory: <current-profile>/deploy/. If an absolute path is given files are searched in the directory.

## Secondary Server Configuration

### FioranoHAKRPCProvider

Presented below are the details for the parameters in **Fiorano->HA->HAKRPCProvider->FioranoHAKRPCProvider->config**

### BackupHAPort

The BackupHAPort parameter specifies the port of the backup peer Server on which the peer is listens for status requests sent by the Server.

### Valid values:

The default value of the BackupHAPort parameter is **2000**.

**Note:** It is mandatory to have the BackupHAPort parameter to run HA.

---

## BackupHAIPAddress

The BackupHAIPAddress parameter specifies the IP address of the backup peer Server on which the peer listens for status requests sent by the Server.

### Valid values:

The default value of the BackupHAIPAddress parameter is **localhost**.

**Note:** It is mandatory to have the BackupHAIPAddress parameter to run HA.

## SocketTimeout

The SocketTimeOut parameter indicates the time in milliseconds before the socket created for communication with the peer Server times out occurs.

### Valid values:

The default value for the SocketTimeOut parameter is **30000**.

The range of integer values considered valid by the SocketTimeout are  $-2^{31}$  to  $2^{31} - 1$

All values less than zero retrieve the same result.

## SocketCreationTimeout

The SocketCreationTimeout indicates the time in milliseconds within which socket must connect with the peer Server failing which the socket creation attempt fails.

### Valid values:

The default value for the SocketCreationTimeout is **30000**.

The range of integer values considered valid by the SocketCreationTimeout are  $-2^{31}$  to  $2^{31} - 1$ .

All values less than zero retrieve the same result.

## FioranoHAConnectionManager

Presented below are the details for the parameters in **Fiorano->HA->HAConnectionManager->FioranoHAConnectionManager->config**

### Port

The Port parameter specifies the port on which the HA Manager listens on for connections from the peer HA Server. This parameter listens for a connection from HA Peer Server in order to know the status of its peer.

---

**Valid values:**

The default value of the Port parameter is **3000**.

The range of integer values considered valid by the Port parameter in java are  $-2^{31}$  to  $2^{31}-1$ .

**Note:** The port may not be used by other services when being used to listen to Peer servers.

### NagleAlgo

The NagleAlgo parameter is a boolean value that determines whether Nagle's Algorithm is enabled during socket creation with peer HA Server. Nagle's algorithm is used in TCP/IP networks for congestion control. It works by coalescing a number of small outgoing messages and sending them together, all at once. If there is a **sent packet** for which the sender has received no acknowledgment, the sender should keep buffering its output until it has a full packet worth of output, so as to send the entire output in one go.

**Valid values:**

The default value for the NagleAlgo parameter is **no**.

- **yes** – Indicates that the NagleAlgo is enabled.
- **no** – Indicates that the NagleAlgo is not enabled.

**Example:**

The Nagle algorithm should not be enabled in situations involving **Delayed ACK** as that will cause TCP performance problems.

### SocketInitializationTimeout

The SocketInitializationTimeout parameter indicates the time in milliseconds within which a client socket should identify itself and exchange its version number with the Server. The version number exchange is an authentication mechanism that FioranoMQ employs.

**Valid values:**

The default value for the SocketInitializationTimeout parameter is **60000** (which is equal to one minute).

The range of integer values considered valid by the SocketInitializationTimeout parameter in java are  $-2^{31}$  to  $2^{31}-1$ .

All values less than zero retrieve the same result.

### FioranoHAManager

Presented below are the details for the parameters in **Fiorano->HA->HAManager->FioranoHAManager->config**

---

## Primary

The Primary parameter is a boolean parameter that indicates whether the acting Server acts as the primary HA Server when in the Replication HA mode. In FioranoMQ's HA implementation, one of the two HA Servers is the primary server while the other is the secondary Server. For more information about FioranoMQ's HA implementation, please refer to *FioranoMQ Concepts Guide Chapter 16* or *FioranoMQ High Availability Guide*.

### Valid values:

The default value of the Primary parameter is **no**.

- **yes** - Indicates that the Server is the primary server.
- **no** - Indicates that the Server is the secondary server.

## GatewayListenerNotUpMesg

In FioranoMQ's HA implementation a gateway machine is used to detect the HA Server which is no longer available on the network. It becomes imperative to choose the gateway machine which itself is least expected to be out of network. It makes sense to use the actual gateway server of the network in which enterprise server is deployed as the Gateway machine for HA.

This parameter helps specify the message which will be displayed when the owning server finds that no listener is present on the configured port but machine is up.

### Valid values:

Default value is **Connection refused**

Any String

## GatewayServerPort

In FioranoMQ's HA implementation a gateway machine is used to detect the HA Server which is no longer available on the network. It becomes imperative to choose the gateway machine which itself is least expected to be out of network. It makes sense to use the actual gateway server of the network in which enterprise server is deployed as the Gateway machine for HA.

This parameter helps specify the port on which Gateway machine is listening for incoming requests.

### Valid values:

Default value is **7**

**Legal values:** range of integer values in java. ( $-2^{31}$  to  $2^{31} - 1$ )

**Note:** The port must not be anything that is being used already, obviously.

---

## PingInterval

The acting HA Server pings its peer Server intermittently to exchange status information. PingInterval is the time interval in milliseconds after which the remote Server is pinged in Replication HA mode.

### Valid values:

The default value for the PingInterval parameter is **30000**.

The range of integer values considered valid by the PingInterval are  $-2^{31}$  to  $2^{31} - 1$ . All values less than zero retrieve the same result.

## SocketCreationTimeout

The SocketCreationTimeout indicates the time in milliseconds within which socket must connect with the peer Server failing which the socket creation attempt fails.

### Valid values:

The default value for the SocketCreationTimeout is **10000**.

The range of integer values considered valid by the SocketCreationTimeout are  $-2^{31}$  to  $2^{31} - 1$ .

All values less than zero retrieve the same result.

## ServerName

The ServerName parameter specifies the name of the Server running in the Replication HA mode.

### Valid values:

The default value for the ServerName is **FMQServer**

Any String may be used as a valid value for this parameter.

### Example:

Naming the server in the most relevant way that explains its purpose makes distinguishing it from other servers easier.

## GatewayServerIPAddress

In FioranoMQ's HA implementation a gateway machine is used to detect the HA Server which is no longer available on the network. It makes sense to use the actual gateway Server of the network in which the enterprise Server is deployed as the Gateway machine for HA.

The GatewayServerIPAddress parameter helps specify the IP address on which the Gateway machine listens for incoming requests.

---

**Valid values:**

The default value for the GatewayServerIPAddress parameter is **localhost**.

**Example:**

Choose a machine that is least expected to be out of the network to ensure that it is most likely to perform its function as a Gateway machine.

In FioranoMQ's HA implementation a gateway machine is used to detect the HA Server which is no longer available on the network. It makes sense to use the actual gateway Server of the network in which the enterprise Server is deployed as the Gateway machine for HA.

The GatewayServerIPAddress parameter helps specify the IP address on which the Gateway machine listens for incoming requests.

**Valid values:**

The default value for the GatewayServerIPAddress parameter is **localhost**.

**Example:**

Choose a machine that is least expected to be out of the network to ensure that it is most likely to perform its function as a Gateway machine.

## FioranoFMQKernel

Presented below are the details for the parameters in **Fiorano->HA->FMQKernel->FioranoFMQKernel->config**

### MQUnDeploymentLists

While in the Active mode the HA Server works normally. While in the Passive mode, the HA Server only monitors its peer and does not handle any client requests. All client connections to the Server when it is in the Passive mode are refused. If a peer Server goes dead the acting Server goes into the Standalone state. In order to **not accept any client connections** while in the Passive state, a few components of the Server need to be undeployed.

These components are listed in FioranoMQ specified files. The MQUnDeploymentLists parameter helps specify lists of files (separated by commas) containing Fiorano specific components that are to be undeployed when necessary.

**Valid values:**

The default value for the MQUnDeploymentLists parameter is **kernel.lst,DefaultMQObjects.lst**.

A comma separated list of .lst files is a valid value for this parameter.

Given a relative path for a file name the files are searched for in the directory: <current-profile>/deploy/. If an absolute path is given files are searched in that directory.

---



## ExternalUnDeploymentLists

When in the Active mode the HA Server works normally. While in the Passive mode, the HA Server only monitors its peer and does not handle any client requests. All client connection to the Server when it is in the Passive mode are refused. If a peer Server goes dead the Server goes into the Standalone state. In order to **not accept any client connections** while in passive state, a few components of the Server need to be undeployed. When the Server is in the Active state these components need to be undeployed.

The components that need to be undeployed are listed in FioranoMQ specified files. The ExternalUnDeploymentLists parameter helps specify lists of files (separated by commas) containing external components that are to be undeployed when necessary.

### Valid values:

The default value for the ExternalUnDeploymentLists parameter is null.

A comma separated list of .lst files is a valid value for this parameter.

Given a relative path for a file name the files are searched for in the directory: <current-profile>/deploy/. If an absolute path is given files are searched in that directory.

## MQDeploymentLists

When in the Active mode the HA Server works normally. While in the Passive mode, the HA Server only monitors its peer and does not handle any client requests. All client connections to the Server when it is in the Passive mode are refused. If a peer Server goes dead then the acting Server goes into the Standalone state. In order to **not accept any client connections** while in passive state, a few components of the Server need to be undeployed. These components are redeployed when the Server starts accepting connections.

The components that need to be redeployed are listed in FioranoMQ specified files. The MQDeploymentLists parameter helps specify lists of files (separated by commas) containing Fiorano specific components that are to be redeployed when necessary.

### Valid values

The default value MQDeploymentLists parameter is **kernel.lst,DefaultMQObjects.lst**

A comma separated list of .lst files is a valid value for this parameter.

Given a relative path for a file name the files are searched for in the directory: <current-profile>/deploy/. If an absolute path is given files are searched in that directory.

---

## ExternalDeploymentLists

When in the Active mode the HA Server works normally. While in the Passive mode, the HA Server only monitors its peer and does not handle any client requests. All client connections to the Server when it is in the Passive mode are refused. In case a peer Server goes dead the acting Server goes into the Standalone state. In order to **not accept any client connections** while in the Passive state, a few components of the Server need to be undeployed. There may be external components that need to be redeployed when the Server goes back to the Active state.

The components to be undeployed are listed in Fiorano files. The ExternalDeploymentLists parameter helps specify lists of files (separated by commas) containing external components that are to be redeployed when necessary.

### Valid values:

The default value for the ExternalDeploymentLists parameter is null.

A comma separated list of .lst files is a valid value for this parameter.

Given a relative path for a file name the files are searched for in the directory: <current-profile>/deploy/. If an absolute path is given files are searched in the directory.

# Chapter 13: Dispatcher Configuration

---

This chapter explains the parameters that can be configured for the FioranoMQ Dispatcher which is used for dispatching incoming connections for load-balancing purposes. These are the various parameters that are configured under the **FioranoMQ→Fiorano→Dispatcher→\*** tree node in the Dispatcher Profile in Offline configuration using Studio.

For more information on FioranoMQ Dispatcher, refer to **Chapter 10 Dispatcher** of *FioranoMQ Handbook*.

## FioranoJobManager2

Presented below are the details for the parameters present in **Fiorano->JobManager->Impl2->FioranoJobManager2->config**.

### MinimumJobWorkers

The MinimumJobWorkers parameter is used to specify the minimum number of job workers to be added when the server is started and remain in the system at any given point of time. This parameter can be increased or decreased depending on the load on each server.

#### Valid values:

The default value is for the MinimumJobWorkers parameter is **4**.

The range of integer values considered valid by the MinimumJobWorkers are  $-2^{31}$  to  $2^{31} - 1$ .

All values less than zero retrieve the same result.

#### Example:

If the server is expected to handle a large number of queues/topics simultaneously, the MinimumJobWorkers parameter may be set at a higher number so as to ensure that this would not result in idle JobWorkers. Similarly, where the load of the server is expected to be little, the number can be decreased.

### MaximumJobWorkers

The MaximumJobWorkers parameter allows the User to set the limit on the number of JobWorkers allowed.. The MaximumJobWorkers parameter can be increased or decreased depending on the expected load on each server.

#### Valid values:

The default value of the MaximumJobWorkers parameter is **40**.

---

The range of integer values considered valid by the MaximumJobWorkers are  $-2^{31}$  to  $2^{31} - 1$ .

All values less than zero retrieve the same result.

#### **Example:**

Allowing unchecked addition of JobWorkers could result in too many threads of JobWorkers being created thus hampering the performance of the system. Depending on the requirements the value for number of JobWorkers allowed can be increased or decreased.

## Dispatcher

Presented below are the details for the parameters present in **Fiorano->Dispatcher->config**.

### Name

This parameter is used to specify the name of the dispatcher.

#### **Valid values:**

The default value of the Dispatcher parameter is **FioranoMQ Dispatcher**.

Any String may be used as a valid value for this parameter.

### PingTimeoutAttribute

The PingTimeoutAttribute parameter describes the time in milliseconds after which the server is pinged.

The dispatcher has to make sure that the server it is connected to is alive, and this is achieved through pinging the Server intermittently. This intermittent time interval is specified by this parameter.

#### **Valid values:**

The default value of the PingTimeout Attribute is **30000**.

The range of integer values considered valid by the PingTimeoutAttribute are  $-2^{31}$  to  $2^{31} - 1$ .

All values less than zero retrieve the same result.

### InitialTimeoutAttribute

The InitialTimeoutAttribute parameter describes the initial timeout in milliseconds in connecting with a server. The dispatcher will time out if it cannot connect to the server within this time.

---

**Valid values:**

The default value of the InitialTimeoutAttribute is **2000**.

The range of integer values considered valid by the InitialTimeoutAttribute are  $-2^{31}$  to  $2^{31}-1$ .

All values less than zero retrieve the same result.

# Chapter 14: Repeater Configuration

---

This chapter explains the parameters that can be configured for the FioranoMQ Repeater that is used for exchanging information between different MQ Servers connected in a particular network topology such as hub-spoke, mesh or bus-based. These are the various parameters that are configured under the **FioranoMQ→Fiorano→Repeater→\*** tree node in the Repeater Profile in Offline configuration using Studio.

For more information on FioranoMQ Repeater, refer to **Chapter 11 Repeater** of *FioranoMQ Handbook*.

## FioranoRepeaterManager

Presented below are the details for the parameters present in **Fiorano->Repeater->RepeaterManager->FioranoRepeaterManager->config**.

### Name

This parameter is used to specify the name of the Repeater Instance.

#### Valid values:

The default value of the Dispatcher parameter is **Repeater**.

Any String may be used as a valid value for this parameter.

### DurableSubscriptionInfoFileName

The DurableSubscriptionInfoFileName parameter is used to specify the name of the XML file that contains information related to durable subscriptions.

#### Valid values:

The default value of the DurableSubscriptionInfoFileName is **rp\_durable.xml**.

Any valid xml filename is an acceptable parameter.

Given a relative path for a filename the Server looks for the xml file in the directory specified in the system property FMQ\_CONFIG\_PATH. If an absolute path for a filename then that file is used.

### PingInterval

The PingInterval parameter describes the time out in milliseconds after which the connection to the Server is pinged.

---

The repeater makes sure that the Server it connected to is still alive by pinging it intermittently. The time interval between pings is specified by this parameter.

**Valid values:**

The default value for the PingInterval parameter is **10000**.

The range of integer values considered valid by the PingInterval are  $-2^{31}$  to  $2^{31} - 1$ .

All values less than zero retrieve the same result.

## AvoidLoopback

The AvoidLoopback parameter is used to specify whether cyclic links are valid in the repeater.

Loopback occurs when there are a set of links connecting FioranoMQ Servers so as to allow the formation of a "cycle". If a message were to originate at a particular FioranoMQ Server then the message would traverse the entire cycle and return to the originating Server. If AvoidLoopback is enabled the message will not be transferred further. If AvoidLoopback is not enabled the message stays within the cycle indefinitely.

**Valid values:**

The default value of the AvoidLoopback parameter is **yes**.

- **yes** - Loopback is avoided.
- **no** - Loopback is not avoided.

## TransactionSize

The TransactionSize parameter is used to specify the number of messages that will amount to a complete transaction.

**Valid values:**

The default value of the TransactionSize parameter is **0**.

The range of integer values considered valid by the PingInterval are  $-2^{31}$  to  $2^{31} - 1$ .

All values less than zero retrieve the same result.

## TransactionTimeout

In a transaction a group of messages together are seen as one transaction. If a message which is a part of the transaction is not received by the subscriber within the TransactionTimeoutPeriod timeout period specified in milliseconds, the transaction commits the messages received as a completed transaction.

**Valid values:**

The default value of the TransactionTimeout parameter is **10**.

---

The range of integer values considered valid by the PingInterval are  $-2^{31}$  to  $2^{31} - 1$ .

All values less than zero retrieve the same result.

## SourceServer

Presented below are the details for the parameters present in **Fiorano->Repeater->FioranoRepeaterManager->Link->SourceServer**.

### Name

This parameter is used to specify the name of the source of the FioranoMQ Server.

#### Valid values:

The default value of the Dispatcher parameter is **LocalhostSourceServer**.

Any String may be used as a valid value for this parameter.

## ConnectionInfo

Presented below are the details for the parameters present in **Fiorano->Repeater->FioranoRepeaterManager->Link->SourceServer->ConnectionInfo**.

### ProtocolType

The ProtocolType parameter describes the underlying protocol to be used to connect to the source of the FioranoMQ Server.

#### Valid values:

The default value of the ProtocolType Server is **TCP**.

### JMXProtocol

The JMXProtocol parameter describes the underlying communication protocol that is used for to connect theJMX connection to the Source FioranoMQ Server.

#### Valid values:

The default value of the JMXProtocol is **rmi**.

### JMXPort

The JMXPort parameter specifies the JMX port hosting the Source FioranoMQ Server, to which a JMX connection is made.

---



**Valid values:**

The default value of this parameter is **1858**.

The range of integer values considered valid by the PingInterval are  $-2^{31}$  to  $2^{31} - 1$ .

All values less than zero retrieve the same result.

## ServerURL

The ServerURL parameter specifies the URL of the FioranoMQ Server that will be a part of a link. The FioranoMQ Server identified ten serves as the source Server in the link.

**Valid values:**

The default value of the ServerURL is **http://localhost:1856**.

Format: http://hostname:port

## UserName

The UserName parameter specifies the login name used by the repeater to connect to the source FioranoMQ Server.

**Valid values:**

The default value of the UserName parameter is **anonymous**.

Any String may be used as a valid value for this parameter.

## Password

The Password parameter specifies the login name used by the repeater to connect to the source FioranoMQ Server.

**Valid values:**

The default value of the password parameter is **anonymous**.

Any String may be used as a valid value for this parameter.

## TopicConnectionFactory

The TopicConnectionFactory parameter specifies the topic connection factory used by the repeater to connect to the source FioranoMQ Server.

**Valid values:**

The default value of the TopicConnectionFactory parameter is **primaryTCF**.

---

Any String may be used as a valid value for this parameter.

## ServerSecurityManager

The ServerSecurityManager parameter specifies the Security Manager used by the source FioranoMQ Server.

### Valid values:

The default value of the ServerSecurityManager parameter is **null**.

Any String may be used as a valid value for this parameter.

## ProxyURLAttribute

The ProxyURLAttribute parameter specifies the URLs of the proxy Servers that are to be used. Multiple backup URLs may be specified as a semicolon-separated string of URLs.

### Valid values:

The default value of the ProxyURLAttribute is **null**.

## ServerSecurityManager parameter LinkTopicInfo

Presented below are the details for the parameters present in **Fiorano->Repeater->FioranoRepeaterManager->Link->LinkTopicInfo**.

## IsDurable

The IsDurable parameter specifies whether the link between the source and the target Server is durable. A durable link ensures that no messages are lost across the repeater in case of network failure.

### Valid values:

The default value of the IsDurable parameter is **false**.

- **true** - Link is durable
- **false** - Link is not durable

## ConnectionMode

The ConnectionMode parameter specifies whether the same JMS connection will be used for replicating the data across JMS Servers or if a separate connection will be created to be used for each link.

---

**Valid values:**

The default value of the ConnectionMode parameter is **Shared**.

- Shared - In this mode the repeater will use the same JMS connection for replicating the data across JMS Servers.
- Exclusive - In this mode the repeater will use separate JMS connections for replicating data across servers. In the exclusive connection mode, a new Replication Link is added for each link.

**Example:**

The Shared connection mode can be used when the replication is directed towards multiple topics on a destination. A single connection is used for all the multiple topics.

## Type

The Type parameter specifies if a link should be permanently connected to the target Server or if the link should when a subscriber exists.

**Valid values:**

The default value for the Type parameter is **SUBSCRIBER EXISTS**.

- SUBSCRIBEREXISTS - The link with the target server that is used for replication does not exist unless there is a subscriber present on that target server.
- ALWAYS - The link that the repeater has with the server will be a permanent link.

## ReplyOn

The ReplyOn parameter specifies the destination on which the repeater listens for replies to requests it forwards.

**Valid values:**

The default value is **null**.

## SourceTopicName

The SourceTopicName parameter specifies the name of the topic on which subscriptions are made on source Server of the link.

**Valid values:**

The default value of the SourceTopicName is **primaryTopic**.

## TargetTopicName

The TargetTopicName parameter specifies the name of the topic on the target server where messages are replicated.

---

**Valid values:**

The default value of the TargetTopicNameParameter is **secondaryTopic**.

**MessageSelector**

The MessageSelector parameter specifies the selector that is set on a link between the Servers that ensures only the required messages are exchanged between Servers.

**Valid values:**

The default value of the MessageSelector parameter is **null**.

Only messages where header and property values match those of the selector will be readable. A message selector matches a message if the selector arrives as **true** when the message header values and property values are substituted by their corresponding identifiers by the selector. If the value of a message selector is an empty string, the value is treated as a null and indicates that there is no message selector for the message consumer.

---

# Chapter 15: Bridge Configurations

---

This chapter explains the parameters that can be configured for the FioranoMQ Bridge which enables inter-operability between FioranoMQ and different messaging queue vendors. These are the various parameters that are configured under the **FioranoMQ→Fiorano→Bridge→\*** tree node in the Bridge Profile in Offline configuration using Studio.

For more information on FioranoMQ Bridge, refer to **Chapter 12 Bridge** of *FioranoMQ Handbook*.

## ConnectionInfo

Presented below are the details for the parameters present in **Fiorano->Bridge->FioranoBridge->FioranoConnectionManager->config-><LinkName>-><ServerName>->ConnectionInfo**.

### ServerType

The ServerType parameter is needed to mention the type of the Server being used.

#### Default Value:

JMS - The default type of server.

### ProviderUrl

The ProviderURL value specifies where the Server is currently running.

The ProviderUrl parameter allows the User to configure the bridge that links the queues present on different FioranoMQ Servers. The URL of the source/target Server should be given here.

#### Default Value:

http://localhost:1856 - The default provider URL of the server.

### InitialContextFactory

The InitialContextFactory parameter specifies the class name of the initial context factory which is used to open connection with the specified Server.

#### Default Value:

fiorano.jms.runtime.naming.FioranoInitialContextFactory - The initial context factory class used.

---

## BridgeUser

The BridgeUser parameter is the User Name which the bridge uses to connect to the Server.

### Default Value:

**Anonymous** - The default bridge user name.

## BridgePassword

The BridgePassword is the password which the bridge uses to connect to the Server.

### Default Value:

**Anonymous** - The default password.

## QCF

The QCF parameter specifies the connection factory with which the connection is to be established.

### Default Value:

**primaryQCF** - The default connection factory used for forming the connection.

## Protocol

The Protocol parameter specifies the transport protocol used for establishing a connection with the Server.

### Default Value:

**TCP** - The default transport protocol used for the connection.

## SecurityPrincipal

The SecurityPrincipal parameter is the User Name used to connect to the Server.

### Default Value:

**ayrton** - The default username.

## SecurityCredentials

The SecurityCredentials parameter is the Password used to connect to the Server.

### Default Value:

**Senna** - The default password.

---

## ServerSecurityManager

The ServerSecurityManager parameter is the Security Manager of the server linked by a bridge.

### Default Value:

**Null** - No server Security Manager.

## QueueInfo

Presented below are the details for the parameters present in **Fiorano->Bridge->FioranoBridge->FioranoConnectionManager->config-><LinkName>-><ChannelName>-><Target/Source Queue>->QueueInfo.**

## MsgSelector

The message selector of the queue. Allows the user to set message selectors for the source/target queues which have been linked using bridges.

### Default Value:

**Null** - No message selector is used

## QueueName

The QueueName parameter is the name of the queue present in the target/source Server to be linked by the bridge. This parameter allows Users to configure links between different queues available on the server.

### Default Value:

**primaryQueue** - The name of the queue which the bridge links.

---

# Chapter 16: JMX Connector Configuration

---

This chapter explains the various parameters that can be configured for connectors used in the FioranoMQ Server (JMX & RMI) for handling remote connection requests to access/modify server configurations at runtime. These are the various parameters that are configured under the **FioranoMQ→Fiorano→jmx→connector→JMSBasedJMXConnector2** and **FioranoMQ→Fiorano→jmx→connector→RMIBasedJMXConnector** tree nodes in Offline configuration through Studio.

For more information on JMX Connectors, refer **Chapter 3 Connection Management** of *FioranoMQ Concepts Guide*.

## JMS Based Connector Configuration

Presented below are the details for the parameters present in **JMX->Connector->JMSBasedJMXConnector**.

### InterceptorClassName

The InceptorClassName parameter is the Class Name that is used to intercept all jmx calls. When JMX calls arrive at the container, this parameter is used to intercept and process these calls.

#### Default Value:

**fiorano.jmx.connector.FioranoJMXInterceptor** - The name of the class used to intercept all jmx calls.

### SecurityProtocol

The SecurityProtocol is the secure protocol used if the Connector Server the Server is connected to is running on a secure protocol. Example: SUN\_SSL, NO\_SECURITY.

#### Valid values:

- NO\_SECURITY - No Security protocol is used.
- SUN\_SSL - Sun\_SSL is the security protocol that is used.

#### Default Value:

- NO\_SECURITY - No security protocol is used by default.
-



## Protocol

The Protocol parameter is the transport protocol used to connect to the JMS Server. This parameter allows the user to choose between available protocols such as LPC, TCP, and HTTP.

### Valid values:

- TCP - TCP is the transport protocol that is used.
- HTTP - HTTP is the transport protocol that is used.
- LPC - LPC is the transport protocol that is used.

### Default value:

LPC - LPC is the default protocol used to connect to the JMS Server.

## SecurityManagerClass

The SecurityManagerClass parameter is the Security Manager class implementats IFMQSecurityManager.

### Valid values:

**NO\_SECURITY** - No Security Manager class is being used.

**fiorano.jmx.connector.fmq.security.JSSESecurityManager** - The Security Manager class name for Sun\_SSL.

### Default value:

NO\_SECURITY – If the No Security Protocol is used, no the SecurityManagerClass will be used by default. However if a SecurityProtocol is used, say SUN\_SSL, then the corresponding SecurityManagerClass, such as fiorano.jmx.connector.fmq.security.JSSESecurityManager must be used.

### Dependencies:

SecurityProtocol

## QueueConnectionFactory

The QueueConnectionFactory parameter is used by the Connector Server. It can be either LPC enabled or normal. LPC Enabled connectionfactory is used when Connector Server connects to the local server.

### Default value:

**primaryLQCF** - The name of the default QueueConnectionFactory being used.

---

## ServerPort

The ServerPort is the port of the JMS Server to which the ConnectorServer connects.

The ServerPort allows the User to configure the server to run on different ports. When a User has to run two or more servers on the same machine, changing the ServerPort value is mandatory since two servers cannot run from the same port.

### Default value:

**1856** - The default port number of the JMS server.

## ServerAddress

The ServerAddress parameter is the IP of the FioranoMQ Server to which the ConnectorServer connects.

**Note:** ServerAddress should be **localhost/LocalIP/MachineName** when the LPC QueueConnectionFactory is being used.

### Default Value:

**localhost** - The default ServerAddress of the JMS Server.

## Username

The UserName parameter is the User Name that is used to connect to the JMS Server.

### Default Value:

**Admin** – Default username.

## Password

Password is the parameter that serves as the password used to connect to the JMS Server.

## ConnectQueueName

The ConnectQueueName parameter is the Connect Queue Name on which the Connector Server listens for connection requests.

Default Value: **JMX\_CONNECT\_QUEUE**

## RequestQueueName

The RequestQueueName parameter is the Request Queue Name on which the Connector Server listens for jmx queries

Default Value: **JMX\_SERVICE\_QUEUE**

---

## NotifQueueName

The NotifQueueName parameter is the Notification Queue Name on which the Connector Server sends notifications.

Default Value: **JMX\_SERVICE\_QUEUE**

## RMI Based Connector Configuration

Presented below are the details for the parameters present in **JMX->Connector->RMIBasedJMXConnector**.

### RMI ServerPort

The RMIServerPort parameter is the port on which the Mx4J RMIServer connects.

This parameter allows the User to configure the RMI port of the Server. When a User runs two or more Servers on the same machine, changing the RMIServerPort value is mandatory as two Servers cannot run on the same RMI port.

Default Value: **1858** - The default RMI port of the Server.

### InterceptorClassName

The InterceptClassName parameter is the class Name that is used to intercept all jmx calls

Default Value: **fiorano.jmx.connector.FioranoJMXInterceptor** - The name of the class used to intercept all jmx calls.

### RmiPortExportObjects

Port on which Rmi Registry will export the Mx4J RMIServer stubs. If set to 0, stubs will be exported at a random port at runtime.

Default Value: 0

### Hostname

Specifies host name on which the registry would export objects. The system property 'java.rmi.server.hostname' is set to this value before starting the rmi registry.

**Note:** It can take comma separated values too.Example:192.168.1.2, 10.0.0.1

Default Value: null

---

## RmiServerSocketFactoryClassName

This parameter denotes the name of server socket factory class to be used by rmi runtime. This class implements 'java.rmi.server. RMIServerSocketFactory' interface.

Default Value: `fiorano.rmi.serverfac.def.FioranoRMIServerSocketFactory`

## RmiClientSocketFactoryClassName

This parameter denotes the name of client socket factory class to be used by rmi runtime. This class implements 'java.rmi.server. RMIClientSocketFactory' interface.

Default Value: `fiorano.rmi.clientfac.def.FioranoRMIClientSocketFactory`

## JMX Engine Configuration

Presented below are the details for the parameters present in **Fiorano->jmx->engine->JMXEngine->ClientJMXEngine**.

### SecurityProtocol

The SecurityProtocol is the secure protocol used if the Connector Server the Server is connected to is running on a secure protocol. Example: `SUN_SSL,NO_SECURITY`.

#### Valid values:

- `NO_SECURITY` - No Security protocol is used.
- `SUN_SSL` - `Sun_SSL` is the security protocol that is used.

#### Default Value:

`NO_SECURITY` - No security protocol is used by default.

### Protocol

The Protocol parameter is the transport protocol used to connect to the JMS Server. This parameter allows the user to choose between available protocols such as `LPC`, `TCP`, and `HTTP`.

#### Valid values:

- `TCP` - `TCP` is the transport protocol that is used.
- `HTTP` - `HTTP` is the transport protocol that is used.
- `LPC` - `LPC` is the transport protocol that is used.

#### Default value:

`LPC` - `LPC` is the default protocol used to connect to the JMS Server.

---

## SecurityManagerClass

The SecurityManagerClass parameter is the Security Manager class implements IFMQSecurityManager.

### Valid values:

**NO\_SECURITY** - No Security Manager class is being used.

**fiorano.jmx.connector.fmq.security.JSSESecurityManager** - The Security Manager class name for Sun\_SSL.

### Default value:

NO\_SECURITY – If the No Security Protocol is used, no the SecurityManagerClass will be used by default. However if a SecurityProtocol is used, say SUN\_SSL, then the corresponding SecurityManagerClass, such as fiorano.jmx.connector.fmq.security.JSSESecurityManager must be used.

### Dependencies:

SecurityProtocol

## QueueConnectionFactory

The QueueConnectionFactory parameter is used by the Connector Server. It can be either LPC enabled or normal. LPC Enabled connectionfactory is used when Connector Server connects to the local server.

### Default value:

**primaryLQCF** - The name of the default QueueConnectionFactory being used.

## ServerPort

Port of JMS Server to which this ConnectorServer connects.

Allows the user to configure the server to run on different ports (when two or more instances of FioranoMQ Server need to be run on the same box).

### Default value:

**1856** - This is the default server port.

## ServerAddress

The ServerAddress parameter is the IP of the FioranoMQ Server to which the ConnectorServer connects.

**Note:** ServerAddress should be **localhost/LocalIP/MachineName** when the LPC QueueConnectionFactory is being used.

---

**Default Value:**

**localhost** - The default ServerAddress of the JMS Server.

**Username**

The Username parameter is the User Name that is used to connect to the JMS Server.

**Default Value:**

**Admin** – Default username.

**Password**

Password is the parameter that serves as the password used to connect to the JMS Server.

**ConnectQueueName**

The ConnectQueueName parameter is the Connect Queue Name on which the Connector Server listens for connection requests.

Default Value: **JMX\_CONNECT\_QUEUE**

**RequestQueueName**

The RequestQueueName parameter is the Request Queue Name on which the Connector Server listens for jmx queries

Default Value: **JMX\_SERVICE\_QUEUE**

**NotifQueueName**

The NotifQueueName parameter is the Notification Queue Name on which the Connector Server sends notifications.

Default Value: **JMX\_SERVICE\_QUEUE**

---

# Chapter 17: Advanced Configuration

---

This chapter provides information about parameters that are generally configured along with the parameters described in all earlier chapters. All the miscellaneous modules, such as Route Manager, Directory Service, RDBMS Manager, Resource Manager, etc. are described in this chapter.

## Route Manager Configuration

Presented below are the details for the parameters present in **Fiorano->etc->RouteManager**.

### MaxTopicBuffer

The MaxTopicBuffer parameter is the upper limit for the message buffer size in bytes.

This parameter allows the user to specify the buffer size in bytes of the messages in the queue. Depending on the density message traffic this value can be increased or decreased.

#### Default Value:

**131072** - This is the maximum number of bytes that can be stored in the buffer.

## RdbmsManager Configurations

Presented below are the details for the parameters present in **Fiorano->etc->RdbmsManager**.

### URL

The URL parameter is the URL of the database where messages are stored. Please refer to the RDBMS Server documentation for formatting this parameter.

The URL parameter allows the User to set/change the URL of the Database Server.

#### Default Value:

**jdbc:hsqldb:../profiles/FioranoMQ/run/RDBMS/FMQ** – This is the default URL of the FioranoMQ RDBMS.

### JdbcDriver

The JdbcDriver is the parameter that is used for RDBMS based Data Storage. Please refer to the Database Driver documentation for formatting this parameter.

**Default Value:**

**org.hsqldb.jdbcDriver** - The default driver used for RDBMS based Data Storage.

## Password

The Password parameter is the password used by a RDBMS User – This is the password used for connecting to the RDBMS Server.

## Username

The Username parameter is the Database User Name used for connecting to the RDBMS Server.

**Default Value:**

Sa

## MaxConnections

The MaxConnections parameter allows a maximum number of Database connections to be created.

The MaxConnections parameter enables restricting the total number of Database connections created. Having too many database connections could affect the performance of the Server.

**Default Value:**

**200** - A maximum of 200 Database connections are allowed at any given point of time.

## DefaultConnections

The DefaultConnections parameter is the number of Database connections created upon starting the Server.

If the User wants to increase the number of Database connections created upon startup, the value of this parameter should be increased.

**Default Value:**

**1** - By default only 1 Database connection is created at startup.

## MaxNoOfRowsFetch

The MaxNoOfRowsFetch parameter specifies the maximum number of rows fetched at a time from the database when a query entered.



When a large number of records needs to be fetched increasing the number of entries fetched per query statement require fewer queries to be entered as more records would be fetched per query.

**Default Value:**

**100** - The maximum number of rows fetched at a shot from the database is 100.

## EnableReconnect

The EnableReconnect parameter which is a boolean indicates whether reconnection needs to be enabled.

The EnableReconnect parameter allows the User to decide whether the Server needs to reconnect to the RDBMS Server when the connection is lost. Where reconnection is not necessary or should not be performed this parameter should be set to False.

**Valid values:**

- **True** - Enables reconnection attempts to the RDBMS Server when connection is lost.
- **False** - Disables reconnection attempts to the RDBMS Server when connection is lost.

**Default Value:**

**True** - Enables reconnection attempts to the RDBMS Server when connection is lost.

## ReconnectTimeInterval

The ReconnectTimeInterval parameter is the time interval in milliseconds between RDBMS reconnection attempts.

The ReconnectTime Interval parameter allows the User to specify the interval between successive reconnection attempts when the connection to the RDBMS Server is down. This value can be increased when the time taken resetting the RDBMS Server is long.

**Default Value:**

**10000** - Time in milliseconds between RDBMS reconnection attempts (which is equivalent to ten seconds).

## WaitTime

The WaitTime parameter is the waiting time if no additional connections are available in the connecting pool. Zero indicates an indefinite waiting time.

The WaitTime parameter allows the User to configure the length of time the server waits to reconnect when the connection pool is empty.

**Default Value:**

**0** - Indicates as infinite/indefinite waiting time.

## ConnectionTimeoutInterval

The ConnectionTimeoutInterval parameter indicates the connection timeout interval in milliseconds.

The ConnectionTimeoutInterval parameter allows the user to configure the connection timeout interval which that is the length of time after when the connection times out if no activity occurs during that period of time.

### Default Value:

**10000** - Connection timeout interval is by default set to ten seconds.

## PropertiesFilename

The PropertiesFilename parameter is the JDBC properties file name. This file contains database specific details for various SQL Types. This parameter needs to include the name of the file jdbc\_\*.cfg available at %FIORANO\_HOME%/fmq/profiles/%PROFILE%/conf directory.

### Default Value:

**jdbc\_hsql.cfg** – This is the default JDBC properties File Name.

## DbConnectivityQuery

The DbConnectivityQuery parameter represents the query that should be executed to check the health of a connection.

The DbConnectivityQuery parameter allows the User to configure the query to be used to test the health/validity of a connection.

### Default Value:

**select \* from tab** - The default query used to check if the connection is alive.

## EnableRdbms

The EnableRdbms parameter enables/disables the Database Manager. Setting this flag to true is a prerequisite for using an RDBMS Server as a back-end message store.

EnableRdbms allows the User to enable/disable the RDBMS message store feature.

### Valid Values:

- **True** - Enables the RDBMS message store.
- **False** - Disables the RDBMS message store.

### Default Value:

**True** - Enables the RDBMS message store.

## Resource Manager Configurations

Presented below are the details for the parameters present in **Fiorano->etc->ResourceManager**.

### MaxMemoryThresholdAllowed

The MaxMemoryThresholdAllowed parameter is the maximum memory threshold that is allowed to be used. The memory threshold value can range from 0.0 to 1.0. This parameter allows the User to set the percentage of total memory that can be used by the server. 1.0 corresponds to 100% and 0.0 corresponds to 0%.

The MaxMemoryThresholdAllowed parameter allows the User to restrict memory usage preventing excessive memory usage by the Server processes.

#### Default Value:

**0.8** - The default memory threshold is set to 80%.

### TimeInterval

The TimeInterval parameter is the time interval after which the monitoring thread runs once again. The time interval is measured in milliseconds.

The TimeInterval parameter allows the User to decide on the intervals between the start of one monitoring thread and the end of the previous one. If the monitoring threads are to be run widely spaced, this parameter should be set to a high value. However, if monitoring is to be done over a short period of time, this parameter should be set to a smaller value.

#### Default Value:

**10000** - A monitoring thread runs once every 10000 milliseconds (which is equivalent to ten seconds).

### EnableMonitoringThread

The EnableMonitoringThread parameter specifies whether the monitoring thread is to be enabled.

The EnableMonitoringThread parameter allows the User to enable/disable the monitoring thread. If the User does not want the monitoring thread to run at periodical intervals, this parameter should be set to False or set to No in Studio.

#### Valid Values:

- **True/Yes** (in Studio) – Enables the running of the monitoring thread at periodic intervals.
- **False/No** (in Studio) - Disables the running of the monitoring thread at periodic intervals.

#### Default Value:

True/Yes (In Studio) - Enables the monitoring thread to be run a periodic intervals.

## EnableVerboseLogging

The EnableVerboseLogging parameter specifies whether to enable/disable verbose logging. If set to false, logs are maintained in the monitor.txt file in the format:[Date][space][Time][comma][QueueConnections][comma][TopicConnections][comma][sessions][comma][senders][comma][receivers][comma][publisher][comma][subscriber][comma][threads][comma][usedMemory].

The EnableVerboseLogging parameter allows the User to choose the format of the logs that are being monitored.

### Valid Values:

- **True/Yes (in Studio)** - Enables Verbose Logging.
- **False/No (in Studio)** - Disables Verbose Logging.

### Default Value:

**True/Yes (in Studio)** - Enables Verbose logging

## EnableThreadDumpInfo

The EnableThreadDump parameter specifies whether to enable/disable thread dump information given the memory in the Server falls below the given threshold.

A User can choose whether to enable the thread dump information using the EnableThreadDump parameter. When the server memory falls below a certain threshold, this parameter should be set to True/Yes (in Studio). If set to True/Yes (in Studio) thread information is dumped into a file so that the User does not loose data.

### Valid Values:

- **True/Yes (in Studio)** - Enables dumping thread information into a file so as not to loose data when the Server is low on memory.
- **True/No (in Studio)** - Disables dumping thread info information into a file so as not to loose data when the Server is low on memory.

### Default Value:

**True/Yes (in Studio)** - Enables the dumping thread info information into a file so as not to loose data when the Server is low on memory.

## PingManager Configurations

Presented below are the details for the parameters present in **Fiorano->etc->PingManager**.

### PingTimeout

The PingTimeout parameter indicates the ping timeout time in milliseconds. The PingTimeout parameter the length of time after which a connection that is disconnected.

This parameter allows the User to configure the length of time after which it should stop trying to connect to a connection that is dead.

Default Value:

**60000** - The number of milliseconds after which a connection that is dead is disconnected.

## JobManager Configurations

### MinimumJobWorkers

The MinimumJobWorkers parameter specifies the minimum number of JobWorkers present at any given time in the system.

The MinimumJobWorkers parameter allows the User to configure the minimum number of JobWorkers that may be added as the Server starts and be present in the system at any given point of time. This parameter can be increased or decreased depending upon the load on each server. If the server is to handle a large number of queues/topics simultaneously, this parameter should be set at a higher number. If the load of the server is expected to be small, this parameter can be decreased so as not to have idle JobWorkers in the system.

Default Value:

**4** - The Minimum number of JobWorkers Available in the system is four.

### MaximumJobWorkers

The MaximumJobWorkers parameter specifies the maximum number of JobWorkers present at any given time in the system.

The MaximumJobWorkers parameter allows the User to configure the maximum number of JobWorkers that may be added as the Server starts and be present in the system at any given point of time. This parameter allows the user to set the limit on the number of JobWorkers allowed in the JobManager. Allowing unchecked additions of JobWorkers could result in too many JobWorkers threads being created, thus hampering the performance of the system. Depending on the scenario, this value of this parameter can be increased or decreased.

**Default Value:**

**40** - The Maximum number of JobWorkers available in the system is 40.

### JobsPerWorker

The JobPerWorker parameter indicates the number of jobs per worker.

This parameter is used to decide whether or not to add more JobWorkers. If the number of jobs present in the job queue becomes larger than the number of job workers present, then new JobWorkers are added. The maximum number of job workers that may be present at any given time cannot exceed 19. The value of the maximum job workers allowed in the system cannot be changed.

Default Value:

**4** - The default number of jobs assigned per job worker at any point of time is 4.

## ObjectManager Configurations

Presented below are the details for the parameters present in **Fiorano->etc->runTimeObjectManagers->ObjectManager/gmsObjectManager**.

### HashCodeReuseAlgoUsed

The HashcodeReuseAlgoUsed parameter indicates whether the Reuse Hash Code Algorithm is used creating Object Handles.

#### Valid Values:

- **True/Yes (in Studio)** – HashcodeReuse Algorithm is used.
- **False/No (in Studio)** - HashcodeReuse Algorithm is not used.

#### Default Value:

**True/Yes (in Studio)** - The hash code reuse algo is used in the creation of Object Handles.

## ThreadManager Configurations

Presented below are the details for Following are the parameters present in **Fiorano->etc->ThreadManager**.

### DelayBetweenAttempts

The DelayBetweenAttempts parameter is the delay in milliseconds between two successive attempts to create a thread when the initial thread creation of a critical operation thread has failed.

If, the creation of a critical operation thread fails, the DelayBetweenAttempts parameter along with the MaximumAttempts parameter ensures that further attempts to create the thread do not affect the performance of the Server.

#### Default Value:

**100** – There is a 100 milliseconds delay between successive attempts to create a thread.

**Dependencies:**

MaximumAttempts

### MaximumAttempts

The MaximumAttempts parameter specifies the maximum number of tries to be attempted to create a thread.

If the creation of a thread results in a failure, after the specified time interval, called the DelayBetweenAttempts parameter, another attempt is made to create the thread. The number of attempts to be made in creating a thread are specifies (and controlled) by this parameter.

**Default Value:**

**8** – The maximum number of attempts to be made to create a thread, before reporting failure of thread creation, is eight.

**Dependencies:**

DelayBetweenAttempts

### MaxIdleThreads

Maximum number of idle threads in thread pool.

Idle threads more than this number are automatically deleted. This ensures that the thread pool does not become too populated with idle threads.

**Default Value:**

4 - A Maximum of 4 threads can remain idle in the thread pool.

## DefaultLogManager Configurations

Presented below are the details for the parameters present in **Fiorano->etc->ClientLogManager->DefaultLogManager**.

Logging into FioranoMQ is achieved with the help of Log4J. Logging in using Log4J makes it possible to enable logging at runtime without modifying the application binaries.

### LogDir

The LogDir parameter is the Base Directory where logs are stored.

The LogDir parameter allows the User to specify the directory in which the logs are to be stored.

Default Value: ../profiles/FioranoMQ/run/logs/ - The directory where logs are stored in FioranoMQ.

## Encoding

The Encoding parameter identifies the Name of the character encoding that is used.

The Encoding parameter allows the User to specify the character encoding to be used when saving logs. This parameter should be set before logs are written and saved.

### Default Value:

**UTF-8** - The default character encoding is UTF-8.

## Level

The Level parameter is the log level that is used by newly constructed handler objects.

The Level parameter allows the User to increase or decrease the log level. Increasing the log level allows more detailed information on any errors or warnings that occur to be displayed. Decreasing the log level briefer error information messages to be displayed.

### Valid Values:

- **-1 to 6 and 10** - Any integer between Zero and six. 10 is the highest integer that may be used. -1.0 is the lowest integer that may be used. All log entries are logged at a particular log level. Each logger has an associated logging level which may be anyone of the following values:
- -1 INHERIT - Inherits log level from its parent.
- QUIET - No logged information.
- FATAL - Severe errors that might cause premature termination.
- ERROR - Other runtime errors or unexpected conditions.
- WARN - Use of deprecated APIs, poor use of API, almost errors, other runtime situations that are undesirable or unexpected but not necessarily wrong.
- INFO - Interesting runtime events at startup/shutdown.
- DEBUG - Detailed information on **flow** through the system.
- TRACE - More detailed information.
- 10 ALL - All logged information.

### Default Value:

**2** The default log level is two.

## FileSizeLimit

The FileSizeLimit parameter specifies the maximum size of each log file where 0 => infinite. This parameter is used by the File Handler.



The FileSizeLimit parameter allows the user to limit the size of the log file. Restricting storage space by specifying the maximum limit of a log ensures that memory does not run out.

**Default Value:**

0 – Zero = a file size with no size limit.

## FileCount

The FileCount parameter specifies the maximum number of log files that may be created. This parameter is used by the File Handler.

The FileCount parameter allows the User to specify the number of log files that may be created.

**Default Value:**

1 - By default only 1 log file may be created.

## AppendToFile

The AppendToFile parameter specifies the append mode of the File Handler. By default, the append mode of the FileHandler is enabled.

The AppendToFile parameter allows the User to specify whether to append data to log files. If set to false, the entries to be added to the log file are added to a new file each time till the number of files reaches the FileCount specified. After the specified log file, the earliest log file is overwritten with current log entries. The log files keep rotating. If set to true, log entries are appended to the end of the current log file.

**Valid Values:**

- True/Yes (in Studio) - Enables Appending to file.
- False/No (in Studio) - Disables Appending to file.

**Default Value:**

**True/Yes (in Studio)** - Enables Appending to file.

## Formatter

The Formatter parameter specifies the Class Name of the class which is used to format the log files.

**Default Value:**

**fiorano.jms.log2.def.CompactFormatter** - The class used for formatting the log files.

## MQ Default Object Creator Configurations

Presented below are the details for the parameters present in **Fiorano->etc->MQDefaultObjCreator**.

### AutoUpdationAllowedForCFs

The AutoUpdationAllowedForCFs is the parameter that sets the AutoUpdate property for FioranoMQ. The default the ConnectionFactory's parameter is based on the AutoUpdationAllowedForCFs flag. To set this parameter, set the boolean option in ConnectionFactory indicating whether updation is allowed in Connection Factories (CF) during startup.

#### Valid Values:

- True/Yes (in Stuido) – Enables AutoUpdation for default connection factories.
- False/No (in Studio) - Disables AutoUpdation for default connection factories.

#### Default Value:

True/Yes (In Studio) - Enables the AutoUpdate property for FioranoMQ default CFs.

### BackupServerIp

The BackupServerIP parameter specifies the backup server IP. This IP is configured in the backup URL of the default Connection Factories.

The BackupServerIP parameter allows the user to set a backup server IP for the default Connection Factories.

#### Default Value:

No Value - The BackupServerIP parameter is left blank by default. The User can set the Backup Server IP by specifying a value for this parameter.

#### Dependencies:

BackupServerPort

### BackupServerPort

The BackupServerPort parameter specifies the Backup Server port. This port is configured in the backup URL for setting the default Connection Factories.

The BackupServerPort parameter allows the User to set a Backup Server port for the default Connection Factories.

**Default Value:**

-1 - This is the default value of the BackupServerPort parameter but it is an invalid port number and is therefore ignored. To have a valid backupUrl both the BackupServerIP and the BackupServerPort should be valid.

**Dependencies:**

BackupServerIp

## Timer Service Configurations

Presented below are the details for the parameters present in **Fiorano->etc->TimerService**.

### Name

The Name parameter is the name of the timer service.

**Default Value:**

**FioranoTimerService** – is the default name of the timer service.

### ClockTick

The ClockTick parameter is the time period in milliseconds after which scheduling of processes are checked.

The ClockTick parameter is the time interval in milliseconds between successive ticks of the timer's clock. Increasing this value results in fewer scheduling of processes checks.

**Default Value:**

**500** – is the time in milliseconds after which process are checked for scheduling.

## JNDI Configurations

### NativeFileNamingManager

Presented below are the details for the parameters present in **Fiorano->jndi->NamingManager->File->NativeFileNamingManager**.

### DefragmentationLowerThreshold

The DefragmentationLowerThreshold parameter specifies the minimum number of deleted entries for triggering auto-defragmentation of the AdminObjectManager

It is necessary to remove the deleted entries from the cache to prevent the cache from becoming from large. However, cache compaction for each deleted entry should be prevented as this process is quite costly. The minimum number of entries that should be deleted to trigger defragmentation is set by this parameter.

**Default Value:**

**10** - Defragmentation is triggered only when there are a minimum of ten deleted entries.

**Dependencies:**

DefragmentationUpperThreshold. DefragmentationPercentage.

### DefragmentationUpperThreshold

The DefragmentationUpperThreshold parameter is the maximum number of deleted entries after which auto-defragmentation of AdminObjectManager is guaranteed/triggered during start up.

When the number of deleted entries in the cache becomes more than the DefragmentationUpperThreshold parameter, the defragmentation process is triggered. The value should be greater than the DefragmentationLowerThreshold. On the other hand, having this parameter set to a very high value could result in a waste of memory.

**Default Value:**

**15** - Defragmentation is triggered only when there are 15 deleted entries.

DefragmentationLowerThreshold. DefragmentationPercentage.

### DefragmentationPercentage

The DefragmentaionPercentage parameter specifies the threshold percentage for auto-defragmentation during startup when the number of deleted entries fall between the thresholds mentioned above.

When the number of deleted entries becomes more than the DefragmentationLowerThreshold set at 40, defragmentation is not triggered immediately. It is triggered either if the number of deleted entries is more than the DefragmentationUpperLimit, or more than 40 or if the percentage of deleted entries present in the cache becomes more than the value set in the DefragmentationPercentage parameter.

**Default Value:**

**20** - The percentage of deleted entries in the cache should be more than 20% to trigger defragmentation.

### Path

The Path parameter is the root path for this Naming Manager.

**Default Value:**

The directory considered the current directory will become the default root path for the NativeFileNamingManager.

## CacheNamingManager

Presented below are the details for the parameters present in **Fiorano->jndi->CacheNamingManager**.

### TTL

The TTL parameter is the duration in milliseconds when the administrative object remains available within the memory.

The TTL parameter allows the User to determine how long the administrative object entries remain in the cache. Using this parameter the length of time these entries may remain available can be increased. If the data attached to these objects are needed only for a short time the value of this parameter can be reduced.

**Default Value:**

**60000** - is the time in milliseconds when the admin objects remain within the memory. This value is equivalent to 60 seconds.

## XMLFileNamingManager

Presented below are the details for the parameters present in **Fiorano->jndi->XMLFileNamingManager**.

### Path

The Path parameter is the absolute or the relative path of the xml file used in persisting information of administrative objects.

Default Value:

The current directory is considered the default path of the Path parameter.

### Filename

The Filename parameter is the ServiceProvider instance of the profile.

**Default Value:**

admin.xml – is the default xml filename

## LDAPNamingManager

Fiorano->jndi->LDAPNamingManage

### LdapProviderUrl

The LdapProviderUrl parameter is the URL of the LDAP Server from where information related to administrative objects are read.

The LdapProviderUrl parameter allows the user to change the LDAP provider URL.

#### Default Value:

ldap://164.164.128.11:389/ - The default URL of the LDAP Server

### LdapBasedn

The LdapBasedn parameter is the Base Domain Name within the LDAP Server under which all information related to administrative objects is stored.

The LdapBasedn parameter allows the User to set the Base Domain from which information related to the administrative objects may be retrieved.

#### Default Value:

o=fiorano, c=US - is the default Base DomainName within the LDAP Server.

### Principal

The Principal parameter is the User Name that NamingManager uses to connect to the LDAP Server for accessing/storing information related to administrative objects.

The Principal parameter allows the User to set authentication details needed to connect to the LDAP Server.

#### Default Value:

o=fiorano, c=US - The default username with which to connect to the LDAP Server.

### Credentials

The Credentials parameter is the password connected to a specific used to login to a specific LDAP Server.

### LdapInitialCtxFactory

The LdapInitialCtxFactory parameter is the Class Name of the initial context factory which is used to connect with specific LDAP Servers.

**Default Value:**

**com.sun.jndi.ldap.LdapCtxFactory** - The default initial context factory class used for connecting to the LDAP Server.

**LdapPollInterval**

The LdapPollInterval parameter is the TimeInterval after which Naming Manager tries to reconnect to LDAP Server in the event of a connection breakdown.

The LdapPollInterval parameter allows the User to set the time interval after the length of which an attempt to connect to the LDAP Server is made if the connection breakdowns. This value coupled with the LdapPrimaryServerReconnectAttempts set at 64, determines the total amount of time after which no more attempts are made to connect to the Primary Server.

**Default Value:**

**4000** – is the default time interval between successive attempts to connect to the LDAP Server.

**Dependencies:**

LdapPrimaryServerReconnectAttempts.

**LdapPrimaryServerReconnectAttempts**

The LdapPrimaryServerReconnectAttempts parameter specifies the number of reconnect attempts to the Primary Server that Naming Manager makes before trying to connect to the Secondary Server.

The LdapPrimaryServerReconnectAttempts parameter allows the User to decide on the number of attempts to be made to connect to the Primary Server before connecting to the Secondary Server. This value coupled with the LdapPollInterval set at 63, determines the total amount of time after which no more attempts are made to connect to the Primary Server.

**Default Value:** 5

**Dependencies:** LdapPollInterval.

**BackupLdapProviderUrl**

The BackupLdapProviderUrl parameter is the URL of the Backup LDAP Server which Naming Manager tries to connect to when the Primary LDAP Server is not available.

The BackupLdapProviderUrl parameter allows the User to setup the Backup LDAP Server to which the Naming Manager can connect when the Primary LDAP Server is down. After trying to connect to the Primary Server, set by the LdapPrimaryServerReconnectAttempts at 64, attempts, an attempt to establish a connection with the Server running at a URL specified by this parameter will be made.

Dependencies: LdapPrimaryServerReconnectAttempts.

## BackupLdapBasedn

The BackupLdapBasedn parameter specifies the Base Domain Name in the Backup LDAP Server under which all information related to administrative objects is stored.

The BackupLdapBasedn parameter allows the User to set the Base Domain from which information related to the administrative objects may be retrieved.

### Default Value:

o=fiorano, c=US – is the default Base Domain Name within the Backup LDAP Server.

## BackupPrincipal

The BackupPrincipal parameter specifies the User Name used by the NamingManager to connect to the backup LDAP Server for accessing/storing information relating to administrative objects.

The BackupPrincipal parameter allows the User to set authentication details so it can connect to the backup LDAP Server.

### Default Value:

o=fiorano, c=US – is the default username that is used to connect to the backup LDAP Server.

## BackupCredentials

The BackupCredentials is the password with specified login details that the User uses to connects to a specified backup LDAP Server.

## BackupLdapInitialCtxFactory

The BackupLdapInitialCtxFactory is the parameter that specifies the Class Name of the initial context factory that is used to open connections with a specified backup LDAP Server.

### Default Value:

**com.sun.jndi.ldap.LdapCtxFactory** – is the default initial context factory class used to connect to the backup LDAP Server.

## BackupLdapPollInterval

The BackupLdapPollInterval parameter specifies the TimeInterval after which Naming Manager tries to reconnect to backup LDAP Server in the event a connection breakdown.

The BackupLdapPollInterval parameter allows the user to set the time interval after which an attempt to connect to the backup LDAP Server is made in the event of a connection breakdown.



**Default Value:**

**4000** – is the default time interval between successive attempts to connect to the backup LDAP Server.

**TopicCFBaseDn**

The TopicCFBaseDn parameter specifies is the Base Domain name within the LDAP Server under which all topic connection factories are stored.

The TopicCFBaseDn parameter allows the User to set the domain under which the Topic connection factories are stored.

**Default Value:**

o=fiorano, c=US – is the default domain name under which the topic connection factories are stored.

**QueueCFBaseDn**

The QueueCFBaseDn parameter specifies the Base Domain name within the LDAP Server under which all queue connection factories are stored.

The QueueCFBaseDn parameter allows the User to set the domain under which the queue connection factories are stored.

**Default Value:**

o=fiorano, c=US – is the default domain name under which the queue connection factories are stored.

**AdminCFBaseDn**

The AdminCFBaseDn parameter specifies the Base Domain Name within the LDAP Server under which all admin connection factories will be stored.

The AdminCFBaseDn parameter allows the User to set the domain name under which the administrative connection factories are stored.

**Default Value:**

o=fiorano, c=US – is the default domain name under which the administrative connection factories are stored.

**UnifiedCFBaseDn**

The UnifiedCFBaseDn parameter specifies the Base Domain name within the LDAP Server under which all unified connection factories are stored.

The UnifiedCFBaseDn parameter allows the User to set the domain under which the unified connection factories are stored.

**Default Value:**

o=fiorano, c=US – is the default domain name under which the unified connection factories are stored.

### TopicsBaseDn

The TopicsBaseDn parameter specifies the Base Domain name within the LDAP Server under which all topics are stored.

The TopicsBaseDn parameter allows the User to set the domain under which all Topics are stored.

**Default Value:**

o=fiorano, c=US – is the default domain name under which the topics are stored.

### QueueBaseDn

The QueueBaseDn parameter specifies the Base Domain name within the LDAP Server under which all queues are stored

The QueueBaseDn parameter allows the User to set the domain under which all Queues are stored.

**Default Value:**

o=fiorano, c=US – is the default domain name under which queues are stored.

## RDBMSNamingManager

Presented below are the details for the parameters present in **Fiorano->jndi->RDBMSNamingManager**.

### URL

The URL parameter specifies the URL of database server from where information related to administrative objects are read.

The URL parameter allows the User to set/change the URL of the database server.

**Default Value:**

**jdbc:hsqldb:Database** – is the default URL of the database server.

## Password

The Password parameter specifies the password using which a User with specified login details connects to the database Server that is specified.

## Username

The Username parameter specifies the User Name which the Naming Manager uses to connect to the RDBMS for accessing/storing information related to administrative objects.

## DatabaseDriver

The database driver parameter specifies the database driver Class Name used to open connect with the specified RDBMS server.

### Default Value:

**org.hsqldb.jdbcDriver** - is the default database driver class name.

## SQLStatementFile

The SQLStatementFile parameter specifies the Name of the properties file that is used to define the Name-Value properties specific to a particular database.

The SQLStatementFile parameter allows the user to set/change the properties file.

### Default Value:

**nm\_sqls.properties** – is the default properties file used.

## ConnectionLostErrorMessage

The ConnectionLostErrorMessage parameter is the error message that is posted when a connection is lost.

The ConnectionLostErrorMessage parameter allows the User to set custom messages to be displayed when connection to the RDBMS Server is lost.

### Default Value:

**DB\_CONNECTION\_LOST** – is the default connection lost message.

## EnableReconnect

The EnableReconnect parameter specifies whether the Naming Manager has to try to reconnect to the database Server in case of connection breakdown.

The EnableReconnect parameter allows the User to decide whether the Naming Manager should make an attempt to reconnect to the RDBMS Server when the connection is lost. Where reconnection is not necessary or should not be performed this parameter should be set to False.

**Valid Values:**

True - Enables reconnection attempts with the Database Server when the connection is down.

False - Disables reconnection attempts with the Database Server when the connection is down.

**Default Value:**

True - Enables reconnection attempts with the Database Server when the connection is down.

### DatabaseConnectionTimeout

The DatabaseConnectionTimeout parameter specifies the length of time that the Naming Manager will attempt to connect to the Database Server. This parameter value may be increased or decreased as per requirements.

**Default Value:**

**10000** - is the length of time in milliseconds the Naming Manager attempts to connect to the Database Server.

### InitializeDB

The InitializeDB parameter specifies whether to initialize the Database for accessing/storing information related to administrative objects.

**Valid values:**

True - Enables initializing the Database

False - Disables initializing the Database

**Default Value:**

True - Enables initializing the Database.

## Connection Consumer Configuration

### FileDBManager5

Presented below are the details for the parameters present in **Fiorano->mq->connection-consumer->FileDBManager->FileDBManager5**.

## Path

The Path parameter allows consumer configuration to be stored in the file based data storage in a specified path.

### Valid values:

The default value of the Path parameter is **CONN\_CONSUMER**.

The path that is specified is relative to the run directory of FioranoMQ profile.

## DeletedThresholdPercent

The DeletedThresholdPercent specifies the entries to be deleted from a cache that stores and manages the list of all the tables pertaining to consumer related information in the file-storage based table. After repeated modification of the table, old entries in the table are marked as deleted. This value provides a threshold percentage of deleted entries after which the Cache Compaction Process is started so that no deleted entries remain in the table. Since cache compaction involves CPU intensive File operations, the DeletedThresholdPercent should be used with DeletedThresholdCount to ensure it is not invoked too often.

### Valid values:

The default value of the DeletedThresholdPercent parameter is **50**. This indicates that when the ratio of deleted entries to total entries is equal to or greater than 0.5, the Cache compaction process will be invoked.

The range of integer values considered valid by the PingInterval are  $-2^{31}$  to  $2^{31} - 1$ .

### Note:

All values less than zero or equal to zero retrieve the same result.

All values greater than or equal to 100 retrieve the same result.

### Example

Use a factor that best defines the ratio of deleted entries/total entries in the table. If there is good chance that many entries are marked deleted quite often then choose a higher number.

### Dependencies

DeletedThresholdCount.

## DeletedThresholdCount

A cache stores and manages the list of all the tables pertaining to consumer related information in this file-storage based table. After repeated modification of the table, old entries in the table are marked deleted. This value provides a threshold count of deleted entries for starting the Cache Compaction Process, at the end of which the table does not have any deleted entries. Since cache compaction involves CPU intensive File operations, this flag along with DeletedThresholdPercent (No. 2) ensures it is not invoked too often.

### Valid values:

The range of integer values considered valid by the PingInterval are  $-2^{31}$  to  $2^{31} - 1$ .

All values less than or equal to zero retrieve the same result.

### Example

Although the **DeletedThresholdPercent** provides a ratio based method of ensuring that the cache compaction process does not occur too often, it does not provide an absolute lower limit on the number of deleted entries that triggers a cache compaction. It is best to choose a value that is high enough to trigger a cache compaction.

### Dependencies

DeletedThresholdPercent.

## DbTableNamePrefix

The DbTableNamePrefix parameter allows Database Names usually prefixed with a string to be modified.

### Valid values:

Any String. Default value is #.

### Example

If the present state of the Database is to be saved to be used again in the future, modifying the prefix to some other relevant string and changing it back to the original string when it is to be used may be done using the DbTableNamePrefix parameter.

## Directory Service

Presented below are the details for the parameters present in **Fiorano->etc->DirectoryService**.

### EnableCluster

The EnableCluster parameter specifies whether Cluster Manager is to be started along with the FioranoMQ Server.

Default Value: Yes.

### EnableProfileMonitoring

The EnableProfileMonitoring parameter defines whether the configuration changes made to the profiles residing inside the Management Server are to be monitored.

If enabled, all the configurational changes are logged automatically to the file \$DBPATH/logs/profile-monitor.log.

Default Value: no

### DirectoryServiceAddress

The DirectoryServiceAddress parameter sets the IPAddress on which the Cluster Manager runs.

**Default Value:** localhost

### DirectoryServicePort

The DirectoryServicePort parameter sets the port on which the Cluster Manager runs.

**Default Value:** 10389

### SecurityPrincipal

The SecurityPrincipal parameter sets the Security Principal required for creating a connection with the Cluster Manager.

**Default Value:** Uid=admin,ou=system.

### SecurityCredentials

The SecurityCredentials parameter sets the Security Credentials required for creating a connection with the Cluster Manager.

**Default Value:** secret.

### AuthenticationMode

The AuthenticationMode parameter sets the authentication mode to be used to connect with the Cluster Manager.

**Default Value:** simple.

## InstancePath

The InstancePath parameter sets the path of the Instance upon which the Cluster Manager will run.

If set to null, the default value set for the working directory is \$FIORANO\_HOME/DSInstance/\$PROFILE\_NAME.

**Default Value:** null

## SynchPeriodMillis

The SynchPeriodMills parameter sets the synchronization time for the Directory Service in milliseconds.

**Default Value:** 15000

## Monitoring Manager Configuration

Presented below are the details for the parameters present in **Fiorano->jmx->notifications->MonitoringManager**.

### ClockTickForMonitoring

The ClockTickForMonitoring parameter specifies the time interval between monitoring instances in milliseconds. The ClockTickForMonitoring indicates the number of milliseconds after which the timer for monitoring is reset. This parameter sets the time interval in milliseconds between successive monitoring attempts.

Default Value:

**5000** - This is equivalent to five seconds and indicates the default idle time after which the monitoring timer is reset.